

**MINISTRY OF EDUCATION AND SCIENCE OF UKRAINE**

**O. M. BEKETOV NATIONAL UNIVERSITY  
OF URBAN ECONOMY in KHARKIV**

**B. P. Bocharov**

**LECTURE NOTES**

*on the course*

**«COMPUTER GRAPHICS»**

**(in english)**

*(for the 2nd year full-time students for the Bachelor  
by specialty 122 – Computer Science and Information Technology)*

Kharkiv – O. M. Beketov NUUE – 2016

Lecture Notes on the course «Computer Graphics» (in english) (for the 2nd year full-time students for the Bachelor by specialty 122 – Computer Science and Information Technology) / O. M. Beketov National University of Urban Economy in Kharkiv; B. P. Bocharov. – Kharkiv : O. M. Beketov NUUE, 2016. – 104 p.

Author : B. P. Bocharov

Reviewer PhD N. P. Pan

Recommended at the meeting of the Department of Applied Mathematics and Information Technology, protocol №3 of 27.09.2016 year.

# Lecture #1.

## Launching AutoCAD. AutoCAD files and folders

### Operations with AutoCAD Drawings

A quick way to begin a new drawing is to start from scratch, which starts a drawing that uses settings from a default drawing template file.

You can start from scratch from the Create New Drawing dialog box, from the Select Template dialog box, or without using a dialog box at all. In each case, you use either the NEW command or the QNEW command.

### Create New Drawing Dialog Box

The following conditions must be met to display the Create New Drawing dialog box:

- The STARTUP system variable is set to 1 (on).
- The FILEDIA system variable is set to 1 (on).

The dialog box defines the settings for a new drawing. Start from Scratch creates a new drawing using either imperial or metric default settings. Use a Template creates a new drawing using the settings defined in a drawing template you select. Use a Wizard creates a new drawing using the settings you specify in either the Quick or Advanced wizard. (The first option, Open a Drawing, is not available from the NEW command. To open an existing drawing, use OPEN.)



#### – *Start from Scratch*

Starts an empty drawing using default imperial or metric settings (MEASUREINIT system variable). You can change the measurement system for a given drawing by using the MEASUREMENT system variable. The Drawing1.dwg that opens when you start the program is a drawing that is started from scratch.

#### Imperial

Starts a new drawing based on the imperial measurement system. The default drawing boundary (the grid limits) is 12 by 9 inches.

#### Metric

Starts a new drawing based on the metric measurement system. The default drawing boundary (the grid limits) is 429 by 297 millimeters.

#### Tip

Displays a description of the selected measurement setting.



#### – *Use a Template*

Starts a drawing based on a drawing template file. Template drawings store all the settings for a drawing and may also include predefined layers, dimension styles,

and views. Template drawings are distinguished from other drawing files by the .dwt file extension. They are normally kept in the template directory.

Several template drawings are included with this program. You can make additional template drawings by changing the extensions of drawing file names to .dwt.

#### Select a Template

Lists all DWT files that currently exist in the drawing template file location, which is specified in the Options dialog box. Select a file to use as a starting point for your new drawing.

#### Preview

Displays a preview image of the selected file.

#### Browse

Displays the Select a Template File dialog box (a standard file selection dialog box), where you can access template files that are not available in the Select a Template list.

#### Template Description

Displays a description of the selected template. If you create your own template, you can use the Template Options dialog box to specify the text that you want to display here. See the SAVEAS command.



#### *– Use a Wizard*

Sets up a drawing using a step-by-step guide. You can choose from two wizards: Quick Setup and Advanced Setup.

#### Quick Setup

Displays the Quick Setup wizard, in which you can specify the units and area for your new drawing. The Quick Setup wizard also changes settings, such as text height and snap spacing, to an appropriate scale.

#### Advanced Setup

Displays the Advanced Setup wizard, in which you can specify the units, angle, angle measure, angle direction, and area for your new drawing. The Advanced Setup wizard also changes settings, such as text height and snap spacing, to an appropriate scale.

#### Wizard Description

Displays a description of the selected wizard.


## **Standard File Selection Dialog Boxes**

Several commands display standard file selection dialog boxes, in which you can navigate through local and network drives and through FTP sites and Web folders to select files. While each dialog box may vary slightly, following is a list of the possible options.

1. Places List. Provides quick access to predefined locations. You can reorder the icons in the Places list by dragging them to a new position. To add a new icon to Places, drag a folder from the list. Right-click in Places to display a shortcut menu

with options for adding, removing, and modifying icons or restoring default icons that have been removed. Changes to Places affect all standard file selection dialog boxes.

- History. Displays shortcuts to the files most recently accessed from the dialog box. It is recommended that you periodically remove unwanted shortcuts from the History list. Select History, then select the unwanted shortcuts in the Files list and click Delete. To sort the shortcuts by date, click Views Details, and then click the Modified column in the Files list.



- Personal/My Documents. Displays the contents of the Personal or My Documents folder for the current user profile. The name of this location (“Personal” or “My Documents”) depends on your operating system version.
- Favorites. Displays the contents of the Favorites folder for the current user profile. This folder consists of shortcuts to files or folders that you added to Favorites using the Tools Add to Favorites option in the dialog box.
- FTP. Displays the FTP sites that are available for browsing in the standard file selection dialog box. To add FTP locations to this list, or to modify an existing FTP location, click Tools Add/Modify FTP Locations in the dialog box.
- Desktop. Displays the contents of your desktop.
- Buzzsaw. Provides access to Buzzsaw projects. Buzzsaw is a secure Internet-based collaboration and project management service that connects

project teams in different locations. To use Buzzsaw, you must already have a project hosting account on Buzzsaw or be given access to a subscriber's Buzzsaw site. If you do not yet have a project hosting account on Buzzsaw, clicking Buzzsaw displays the Select Template dialog box where you can add a Buzzsaw location shortcut. Double-clicking Add a Buzzsaw Location Shortcut opens the Log In To Buzzsaw dialog box where you can register for a free 30-day trial subscription to the service. Also, the first time you access Buzzsaw, your default web browser opens with the project hosting page displayed. If you already have a project hosting account, clicking Buzzsaw shows all of your project sites in the Site list.


2. Look In/Save In. Displays the current folder or drive. Click the arrow to view the hierarchy of the folder path and to navigate up the path tree or to other drives, network connections, FTP locations, or web folders (either Web Folders or My Network Places, depending on the version of your operating system). You can create web folders in Windows Explorer. Consult your system administrator or Windows Explorer Help for more information about web folders. To control whether the last used paths in each particular standard file selection dialog box are stored across sessions, use the REMEMBERFOLDERS system variable.
3. Back. Returns to the previous file location.
4. Up One Level. Navigates one level up in the current path tree.
5. Search the Web. Displays the Browse the Web dialog box, from which you can access and store files on the Internet.
6. Delete. Deletes the selected file or folder.
7. Create New Folder. Creates a new folder in the current path using a name that you specify.
8. Views. Controls the appearance of the Files list or Folders list and, for a Files list, specifies whether to show a preview image when a file is selected.
  - List. Displays a multicolumn list.
  - Details. Displays a single-column list with file details.
  - Preview. Displays a bitmap of the selected file. The Preview area is blank if you do not select a file. To save a bitmap with a drawing file, use the Save a Thumbnail Preview Image option on the Open and Save tab in the Options dialog box.
9. Tools. Provides tools to help with file selection and other actions available in file selection dialog boxes.
  - Find. Displays the Find dialog box, in which you can search for files using name, location, and date-modified filters.
  - Locate. Uses the AutoCAD search path to locate the file specified in File Name. You set the search path on the Files tab in the Options dialog box.
  - Add/Modify FTP Locations. Displays the Add/Modify FTP Locations dialog box, in which you can specify the FTP sites to make available for browsing. To browse these sites, select FTP from the Places list.
  - Add Current Folder to Places. Adds an icon for the selected folder to the Places list, providing quick access to that folder from all standard file

selection dialog boxes. To remove the icon, right-click the icon and choose Remove.

- Add to Favorites. Creates a shortcut to the current Look In location, or to the selected file or folder. The shortcut is placed in the Favorites folder for the current user profile, which you can access by choosing Favorites in the Places list.
  - Look in Favorites. Sets the Look In path to your system's Favorites folder.
  - Options. Provides additional options for certain standard file selection dialog boxes.
  - Security Options. Provides options for a digital signature and password that are invoked when you save a file.
10. Files List. Displays the files and folders in the current path and of the selected file type. Use the Views menu in the dialog box to switch between List view and Details view.
  11. Preview. Displays a bitmap of the selected file when you choose Views Preview in the dialog box. The Preview area is blank if you do not select a file. To save a bitmap with a drawing file, use the Save a Thumbnail Preview Image option on the Open and Save tab in the Options dialog box.
  12. File Name. Displays the name of the file you select in the Files list. If you select multiple files, File Name displays each selected file within quotation marks. If you enter a file name in the File Name box, any selection is cleared. You must use quotation marks when entering multiple file names. You can use wild-card characters to filter files displayed in the Files list.
  13. Files of Type. Filters the list of files by file type. When you are saving files, Files of Type specifies the format in which the file is saved.
  14. Select Initial View. Displays the specified model space view when you open the drawing if the drawing contains more than one named view.
  15. Update Sheet and View Thumbnails Now. Reflects the current setting of the UPDATETHUMBNAIL system variable. This option temporarily overrides that setting. Clear the checkbox to save the file without updating thumbnails. Check the box to update all thumbnails. This option does not change the current setting of UPDATETHUMBNAIL.
  16. Open/Save. Depending on the purpose of the specific file selection dialog box, opens or saves the selected file or enters the path of the selected folder in the previous dialog box. Certain file selection dialog boxes may include additional options, accessed by clicking the arrow next to the Open button.
    - Open Read-Only. Opens a file in read-only mode. You cannot save changes to the file using the original file name.
    - Partial Open. Displays the Partial Open dialog box. You can open and load a portion of a drawing, including geometry on a specific view or layer. PARTIALOPEN cannot be used with a drawing that is not in the latest drawing file format.
    - Partial Open Read-Only. Opens the specified drawing portions in read-only mode.

## Partial Open Dialog Box

The dialog box displays the drawing views and layers available for specifying what geometry to load into the selected drawing. When working with large drawing files, you can select the minimal amount of geometry you need to load when opening a drawing.



When a drawing is partially open, all named objects, as well as the specified geometry, are loaded into the file. Named objects include blocks, dimension styles, layers, layouts, linetypes, text styles, UCSs, views, and viewport configurations.

## Save AutoCAD Drawings

You save drawing files for later use just as you do with other Microsoft Windows applications. You can also set up automatic saving and backup files and save only selected objects.

When you work on a drawing, you should save it frequently. Saving protects you from losing work in the event of a power failure or other unexpected event. If you want to create a new version of a drawing without affecting the original drawing, you can save it under another name.

The file extension for drawing files is .dwg, and unless you change the default file format in which drawings are saved, drawings are saved in the latest drawing file format. This format is optimized for file compression and for use on a network.



The character limit for a DWG file name (including its path) is 256 characters.


If FILEDIA is set to 1 the *Save Drawing As* standard file selection dialog box is displayed. When FILEDIA is set to 0, SAVEAS displays command prompts.

Enter a file name and type.

Note. AutoCAD 2004 is the drawing file format used by the AutoCAD 2004, AutoCAD 2005, and AutoCAD 2006 releases.

In the *Save Drawing As* dialog box, Tools Options displays the Saveas Options dialog box, which controls various DWG and DXF settings.

*DWG Options Tab (Saveas Options Dialog Box)* controls the drawing index and display of custom objects and specifies the default file format for saving drawings.



### Save Proxy Images of Custom Objects


If you save to an earlier drawing file type, or the drawing contains custom objects from another application, you can select Save Proxy Images of Custom Objects to save images of the custom objects in the drawing file. If you do not choose this option, a frame is saved for each custom object in the drawing file. (PROXYGRAPHICS system variable). If you are saving a drawing file that contains DWF references to an earlier drawing format, this switch has no effect on DWF underlays as they will not appear as proxy objects or as a frame.

### Index Type

Determines whether layer or spatial indexes are created when you save a drawing. The indexes are used to improve performance during demand loading. Using indexes may slightly increase the time required to save a drawing. If a partially open drawing does not already contain spatial and layer indexes, this option is not available

The file is saved with the specified file name. If the drawing is already named, the drawing is saved with the new file name. If you save the file as a drawing template, the Template Options dialog box is displayed, where you can provide a description for the template and set the units of measurement.

*Template Options Dialog Box* sets drawing template options.



## Lecture #2.

# AutoCAD interface. Commands input methods, the use of menus and tool bars. Work with layers. Points coordinates input methods.

## The User Interface

You can use several menus, shortcut menus, toolbars, and the dashboard to access frequently used commands, settings, and modes.

## Toolbars

Use buttons on toolbars to start commands, display flyout toolbars, and display tooltips. You can display or hide, dock, and resize toolbars.

Toolbars contain buttons that start commands. When you move your mouse or pointing device over a toolbar button, the tooltip displays the name of the button. Buttons with a small black triangle in the lower-right corner are flyout toolbars that contain related commands. With the cursor over the icon, hold down the left button on your mouse until the flyout toolbar is displayed.

The Standard toolbar at the top of the drawing area is displayed by default. This toolbar is similar to those found in Microsoft Office programs. It contains frequently used AutoCAD commands such as PROPERTIES, PAN, and ZOOM, as well as Microsoft Office standard commands such as New, Open, and Save.

Display or Hide, Dock, and Resize Toolbars. AutoCAD initially displays several toolbars such as

- Standard toolbar
- Styles toolbar
- Layers toolbar

You can display or hide these toolbars and additional ones, and you can save your selections as a workspace. You can also create your own toolbars.

A toolbar can be floating or docked. A floating toolbar is located anywhere in the drawing area, and you can drag a floating toolbar to a new location, resize it, or dock it. A docked toolbar is attached to any edge of the drawing area. You can move a docked toolbar by dragging it to a new docking location.

## Status Bars

The application and drawing status bars provide useful information, buttons for turning on and off drawing tools.

The application status bar displays the coordinate values of your cursor along with several buttons for turning on and off drawing tools and may display tools for scaling annotations. You can choose which buttons you want to display in the status bar.




The drawing status bar displays several tools for scaling annotations.

Different tools display for model space and paper space.

When the drawing status bar is turned on it displays at the bottom of the drawing area. When the drawing status bar is turned off, the tools found on the drawing status bar are moved to the application status bar.

When the drawing status bar is turned on, you can use the InfoBar menu to choose which tools display in status bar.



## The Menu Bar

Display pull-down menus from the menu bar using one of several methods. You can also specify alternate menus.

Menus are available from the menu bar at the top of the AutoCAD drawing area.

To use a menu choose one of the following methods:

- On the menu bar, click a menu name to display a list of options. On the menu, either click an option or use the DOWN ARROW to move down the list, and then press ENTER.
- Press ALT and press the key for the underlined letter in the menu name; then, press the underlined letter in the option name. For example, to open a new drawing, press ALT and press F to open the File menu; then, press N for New.

You can specify menus to display in the program by customizing a CUI file and loading it into the program.

## **Shortcut Menus**

Display a shortcut menu for quick access to commands that are relevant to your current activity.

You can display different shortcut menus when you right-click different areas of the screen, including

- Within the drawing area with or without any objects selected
- Within the drawing area during a command
- Within the text and command windows
- Within areas and on icons in DesignCenter
- Within areas and on text in the In-Place Text Editor
- On a toolbar or tool palette
- On the Model or layout tabs
- On the status bar or the status bar buttons
- In certain dialog boxes

Shortcut menus typically include options to


- Repeat the last command entered
- Cancel the current command
- Display a list of recent user input
- Cut, copy, and paste from the Clipboard
- Select a different command option
- Display a dialog box, such as Options or Customize
- Undo the last command entered

You can customize right-click behavior to be time-sensitive, so that a quick right-click acts the same as pressing ENTER, and a longer right-click displays a shortcut menu.

Shortcut menus can be customized using a customization (CUI) file. The main CUI file is called acad.cui by default.

## The Dashboard

The dashboard is a special palette that displays buttons and controls that are associated with a task-based workspace.



The dashboard provides a single interface element for operations that are relevant to the current workspace. The dashboard eliminates the need to display a lot of toolbars and reduces the clutter in the application window. Thus, you can maximize the area available for work, and use a single interface for speed and convenience.

The dashboard opens automatically by default when you use either the 2D Drafting & Annotation workspace or the 3D Modeling workspace. You can open the dashboard manually:

- Click Tools menu ► Palettes ► Dashboard.
- At the Command prompt, enter *dashboard*.

The dashboard is organized into a series of control panels. Each control panel includes related tools and controls that are similar to the tools in toolbars and controls in dialog boxes.

The large icons displayed at the left side of the dashboard are called control panel icons. Each control panel icon identifies the purpose of the control panel. On some control panels, if you click the icon, a slide-out panel opens that contains additional tools and controls. An open slide-out panel closes automatically when you click another control panel icon. Only one slide-out panel is displayed at a time.

A tool palette group can be associated with each control panel. To display the associated tool palette group, click a tool or open a slide-out panel.

You can customize the display of the dashboard (display or hide, dock, and resize the dashboard) in the following ways:

- Size the dashboard horizontally. If not enough space is available to display all the tools in a row, a black down-arrow called an overflow control is displayed.
- Use the shortcut menu to control the auto-hide, docking, and anchoring behavior. With anchoring, the dashboard results is displayed as a narrow space-saving strip along the left or right edge of the drawing area.

You can customize the dashboard in the following ways:

- You can create and modify dashboard panels using the Customize User Interface dialog box.
- You can specify which control panels are displayed by right-clicking the dashboard and, on the shortcut menu, clicking or clearing the names of control panels.
- You can associate a customizable tool palette group with each control panel on the dashboard. Right-click the control panel to display a list of available tool palette groups.

## **Enter Commands on the Command Line**

You can enter a command by using the keyboard. Some commands also have abbreviated names called command aliases.

To enter a command by using the keyboard, type the full command name on the command line and press ENTER or SPACEBAR.

*Note.* When Dynamic Input is on and is set to display dynamic prompts, you can enter many commands in tooltips near the cursor.

Some commands also have abbreviated names. For example, instead of entering line to start the LINE command, you can enter l. Abbreviated command names are called command aliases and are defined in the acad.pgp file.

To find a command, you can type a letter on the command line and press TAB to cycle through all the commands that begin with that letter. Press ENTER or SPACEBAR. Restart a recently used command by right-clicking on the command line.

When you enter commands on the command line, you see either a set of options or a dialog box. For example, when you enter circle at the Command prompt, the following prompt is displayed:

*Specify center point for circle or [3P/2P/Ttr (tan, tan, radius)]:*

You can specify the center point either by entering X,Y coordinate values or by using the pointing device to click a point on the screen.

To choose a different option, enter the letters capitalized in one of the options in the brackets. You can enter uppercase or lowercase letters. For example, to choose the three-point option (3P), enter 3p.

To execute commands, press SPACEBAR or ENTER, or right-click your pointing device after entering command names or responses to prompts. The instructions in Help assume this step and do not specifically instruct you to press ENTER after each entry.

If you want to repeat a command that you have just used, press ENTER or SPACEBAR, or right-click your pointing device at the Command prompt.

You also can repeat a command by entering multiple, a space, and the command name, as shown in the following example:

*Command: multiple circle*

To cancel a command in progress, press ESC.

Many commands can be used transparently: that is, they can be entered on the command line while you use another command. Transparent commands frequently change drawing settings or display options, for example, GRID or ZOOM. In the Command Reference, transparent commands are designated by an apostrophe in front of the command name.

To use a command transparently, click its toolbar button or enter an apostrophe (') before entering the command at any prompt. On the command line, double angle brackets (>>) precede prompts that are displayed for transparent commands. After you complete the transparent command, the original command resumes. In the following example, you turn on the dot grid and set it to one-unit intervals while you draw a line, and then you continue drawing the line.

*Command: line*

*Specify first point: 'grid*

*>>Specify grid spacing (X) or [ON/OFF/Snap/Aspect] <0.000>: 1*

*Resuming LINE command*

*Specify first point:*

Commands that do not select objects, create new objects, or end the drawing session usually can be used transparently. Changes made in dialog boxes that you have opened transparently cannot take effect until the interrupted command has been executed. Similarly, if you reset a system variable transparently, the new value cannot take effect until you start the next command.

## **Enter Coordinates**

Absolute and relative 2D Cartesian and polar coordinates determine precise locations of objects in a drawing.

You can use absolute or relative Cartesian (rectangular) coordinates to locate points when creating objects.

To use *Cartesian* coordinates to specify a point, enter an X value and a Y value separated by a comma (X,Y). The X value is the positive or negative distance, in

units, along the horizontal axis. The Y value is the positive or negative distance, in units, along the vertical axis.

Absolute coordinates are based on the UCS origin (0,0), which is the intersection of the X and Y axes. Use absolute coordinates when you know the precise X and Y values of the point.

With Dynamic Input, you can specify absolute coordinates with the # prefix. If you enter coordinates on the command line instead of in the tooltip, the # prefix is not used. For example, entering #3,4 specifies a point 3 units along the X axis and 4 units along the Y axis from the UCS origin. For more information about Dynamic Input, see *Use Dynamic Input*.


The following example draws a line beginning at an X value of -2, a Y value of 1, and an endpoint at 3,4. Enter the following in the tooltip:

*Command: line*

*From point: #-2,1*

*To point: #3,4*

The line is located as follows:



Relative coordinates are based on the last point entered. Use relative coordinates when you know the location of a point in relation to the previous point.

To specify relative coordinates, precede the coordinate values with an @ sign. For example, entering @3,4 specifies a point 3 units along the X axis and 4 units along the Y axis from the last point specified.

The following example draws the sides of a triangle. The first side is a line starting at the absolute coordinates -2,1 and ending at a point 5 units in the X direction and 0 units in the Y direction. The second side is a line starting at the endpoint of the first line and ending at a point 0 units in the X direction and 3 units in the Y direction. The final line segment uses relative coordinates to return to the starting point.

*Command: line*


*From point: #-2,1*

*To point: @5,0*

*To point: @0,3*

*To point: @-5,-3*





You can use absolute or relative *polar* coordinates (distance and angle) to locate points when creating objects.

To use polar coordinates to specify a point, enter a distance and an angle separated by an angle bracket (<).

By default, angles increase in the counterclockwise direction and decrease in the clockwise direction. To specify a clockwise direction, enter a negative value for the angle. For example, entering 1<315 locates the same point as entering 1<-45. You can change the angle conventions for the current drawing with UNITS.




Absolute polar coordinates are measured from the UCS origin (0,0), which is the intersection of the X and Y axes. Use absolute polar coordinates when you know the precise distance and angle coordinates of the point.

With Dynamic Input, you can specify absolute coordinates with the # prefix. If you enter coordinates on the command line instead of in the tooltip, the # prefix is not used. For example, entering #3<45 specifies a point 3 units from the origin at an angle of 45 degrees from the X axis. For more information about Dynamic Input, see *Use Dynamic Input*.

The following example shows two lines drawn with absolute polar coordinates using the default angle direction setting. Enter the following in the tooltip:

*Command:* line  
*From point:* #0,0  
*To point:* #4<120  
*To point:* #5<30



Relative coordinates are based on the last point entered. Use relative coordinates when you know the location of a point in relation to the previous point.


To specify relative coordinates, precede the coordinate values with an @ sign. For example, entering @1<45 specifies a point at a distance of 1 unit from the last point specified at an angle of 45 degrees from the X axis.

The following example shows two lines drawn with relative polar coordinates. In each illustration, the line begins at the location labeled as the previous point.

*Command: line*

*From point: @3<45*

*To point: @5<285*



### Use Dynamic Input

Dynamic Input provides a command interface near the cursor to help you keep your focus in the drafting area.

When Dynamic Input is on, tooltips display information near the cursor that is dynamically updated as the cursor moves. When a command is active, the tooltips provide a place for user entry.

After you type a value in an input field and press TAB, the field then displays a lock icon, and the cursor is constrained by the value that you entered. You can then enter a value for the second input field. Alternately, if you type a value and press ENTER, the second input field is ignored and the value is interpreted as direct distance entry.

The actions required to complete a command or to use grips are similar to those for the command prompt. The difference is that your attention can stay near the cursor.

Dynamic Input is not designed to replace the command window. You can hide the command window to add screen area for drawing, but you will need to display it for some operations. Press F2

to hide and display command prompts and error messages as needed. Alternately, you can undock the command window and use Auto-hide to roll open or roll up the window.


### Turn Dynamic Input On and Off

Click Dyn on the status bar to turn Dynamic Input on and off. You can turn it off temporarily by holding down the F12 key. Dynamic Input has three components: pointer input, dimensional input, and dynamic prompts. Right-click Dyn and click Settings to control what is displayed by each component when Dynamic Input is on.

#### Pointer Input

When pointer input is on and a command is active, the location of the crosshairs is displayed as coordinates in a tooltip near the cursor. You can enter coordinate values in the tooltip instead of on the command line.


The default for second and subsequent points is relative polar coordinates (relative Cartesian for RECTANG). There is no need to type the at sign (@). If you want to use absolute coordinates, use the pound sign (#) prefix. For example, to move an object to the origin, for the second point prompt, enter #0,0.



Use the pointer input settings to change the default format for coordinates and to control when pointer input tooltips are displayed.

#### Dimensional Input


When dimensional input is on, the tooltips display distance and angle values when a command prompts for a second point. The values in the dimensional tooltips change as you move the cursor. Press TAB to move to the value you want to change. Dimensional input is available for ARC, CIRCLE, ELLIPSE, LINE, and PLINE.



When you use grips to edit an object, the dimensional input tooltips can display the following information:

- Original length
- A length that updates as you move the grip
- The change in the length
- Angle
- The change in the angle as you move the grip
- The radius of an arc

Use the dimensional input settings to display only the information you want to see.



When you use grips to stretch objects or when you create new objects, dimensional input displays only acute angles, that is, all angles are displayed as 180 degrees or less. Thus, an angle of 270 degrees is displayed as 90 degrees regardless of the ANGDIR system variable setting (set in the Drawing Units dialog box). Angles specified when creating new objects rely on the cursor location to determine the positive angle direction.

### Dynamic Prompts

When dynamic prompts are on, prompts are displayed in a tooltip near the cursor. You can enter a response in the tooltip instead of on the command line. Press the DOWN ARROW key to view and select options. Press the UP ARROW key to display recent input.




*Note.* To use PASTECLIP in a dynamic prompt tooltip, type a letter and then backspace to delete it before you paste the entry. Otherwise, the entry is pasted into the drawing as text.

## **Work with Layers**

Layers are like transparent overlays on which you organize and group objects in a drawing.

Layers are used to group information in a drawing by function and to enforce linetype, color, and other standards.

Layers are the equivalent of the overlays used in paper-based drafting. Layers are the primary organizational tool used in drawing. You use layers to group information by function and to enforce linetype, color, and other standards.



By creating layers, you can associate similar types of objects by assigning them to the same layer. For example, you can put construction lines, text, dimensions, and title blocks on separate layers. You can then control the following:

- Whether objects on a layer are visible or dimmed in any viewports
- Whether and how objects are plotted
- What color is assigned to all objects on a layer
- What default linetype and lineweight are assigned to all objects on a layer
- Whether objects on a layer can be modified
- Whether objects display with different layer properties in individual layout viewports

Every drawing includes a layer named 0. Layer 0 cannot be deleted or renamed. It has two purposes:

- Ensure that every drawing includes at least one layer
- Provide a special layer that relates to controlling colors in blocks

**Note. It is recommended that you create several new layers with which to organize your drawing rather than create your entire drawing on layer 0.**

You can use layers to control the visibility of objects and to assign properties to objects. Layers can be locked to prevent objects from being modified.

You can reduce the visual complexity of a drawing and improve display performance by controlling how objects are displayed or plotted. For example, you can use layers to control the properties and visibility of similar objects, such as electrical parts or dimensions. Also, you can lock a layer to prevent objects on that layer from being accidentally selected and modified.

#### Control the Visibility of Objects on a Layer

You can make drawing layers invisible either by turning them off or by freezing them. Turning off or freezing layers is useful if you need an unobstructed view when working in detail on a particular layer or set of layers or if you don't want to plot details such as reference lines. Whether you choose to freeze layers or turn them off depends on how you work and on the size of your drawing.

- *On/Off.* Objects on turned-off layers are invisible, but they still hide objects when you use HIDE. When you turn layers on and off, the drawing is not regenerated.
- *Freeze/Thaw.* Objects on frozen layers are invisible and do not hide other objects. In large drawings, freezing unneeded layers speeds up operations involving display and regeneration. Thawing one or more

layers causes the drawing to be regenerated. Freezing and thawing layers takes more time than turning layers on and off.

In a layout, you can freeze layers in individual layout viewports.

*Note.* Instead of turning off or freezing a layer, you can dim the layer by locking it. See *Lock the Objects on a Layer*.

#### Assign a Default Color and Linetype to a Layer

Each layer has associated properties such as color and linetype that are assumed by all objects on that layer when the setting is ByLayer. For example, if the Color control on the Properties toolbar is set to BYLAYER, the color of new objects is determined by the color setting for the layer in the *Layer Properties Manager*.

If you set a specific color in the Color control, that color is used for all new objects, overriding the default color for the current layer. The same is true for the Linetype, Lineweight, and Plot Style controls on the Properties toolbar.

#### Lock the Objects on a Layer

When a layer is locked, none of the objects on that layer can be modified until you unlock the layer. Locking layers reduces the possibility of modifying objects accidentally. You can still apply object snaps to objects on a locked layer and perform other operations that do not modify those objects.

You can also dim the objects on a locked layer. This serves the following two purposes:



- You can easily see what objects are on locked layers.
- You can reduce the visual complexity of a drawing but still maintain visual reference and object snapping capabilities to those objects.


The LAYLOCKFADECTL system variable controls the dimming applied to locked layers. Locked layers that are dimmed are plotted normally.


*Note.* Grips are not displayed on objects that are on locked layers.


### **Layer Properties Manager**


It displays a list of the layers in the drawing and their properties. You can add, delete, and rename layers, change their properties, set property overrides for layout viewports, or add descriptions. Layer filters control which layers are displayed in the list and can also be used to make changes to more than one layer at a time.


-  New Property Filter displays the Layer Filter Properties dialog box, where you can create a layer filter based on one or more properties of the layers.
-  New Group Filter creates a layer filter that contains layers that you select and add to the filter.




 **Layer States Manager** displays the Layer States Manager, in which you can save the current property settings for layers in a named layer state and then restore those settings later.

 **New Layer** creates a new layer. The list displays a layer named LAYER1. The name is selected so that you can enter a new layer name immediately. The new layer inherits the properties of the currently selected layer in the layer list (color, on or off state, and so on).

 **New Layer Frozen VP In All Viewports** creates a new layer and freezes it in all existing layout viewports. This button is accessible from the Model tab or layout tabs.

 **Delete Layer** marks selected layers for deletion. Layers are deleted when you click Apply or OK. You can delete only unreferenced layers. Referenced layers include layers 0 and DEFPOINTS, layers containing objects (including objects in block definitions), the current layer, and xref-dependent layers. Layers in a partially opened drawing are also considered referenced and cannot be deleted.

*Note.* Be careful about deleting layers if you are working on a drawing in a shared project or one based on a set of layering standards.

 **Set Current** sets the selected layer as the current layer. Objects that you create are drawn on the current layer. (CLAYER system variable).

# Lecture #3.

## Creation of AutoCAD entities. Part 1

### Draw Lines

In a simple *line* with connected segments, each segment is a separate line object.

With LINE, you can create a series of contiguous line segments.

Each single line segment can be edited separately from the other line segments in a series. You can close a sequence of line segments so that the first and last segments are joined.

You specify the locations that define the endpoints of each line with precision. You can

- Enter the coordinate values for an endpoint, using either absolute or relative coordinates
- Specify an object snap relative to an existing object. For example, you can specify the center of a circle as one endpoint of the line
- Turn grid snap on and snap to a location

Use *polyline* objects instead of line objects if you want the segments to be connected as a single object.

#### Using LINE command

Toolbar: Draw



Menu: Draw > Line

Command entry: line

*Specify first point:* Specify a point or press ENTER to continue from the last drawn line or arc

*Specify next point or [Close/Undo]:*

#### **Continue**

Continues a line from the endpoint of the most recently drawn line.




before pressing ENTER



after pressing ENTER

If the most recently drawn line is an arc, its endpoint defines the starting point of the line, and the line is drawn tangent to the arc.





**Close**

Ends the last line segment at the beginning of the first line segment, which forms a closed loop of line segments. You can use Close after you have drawn a series of two or more segments.



**Undo**

Erases the most recent segment of a line sequence.



Entering u more than once backtracks through line segments in the order you created them.


**Drawing with the Line tool examples**

Open AutoCAD. The drawing area will show the settings of the acadiso.dwt template - Limits set to 420,297, Grid set to 10, Snap set to 5 and Units set to 0.

*Left-click* on the **Line** tool in the **2D Draw** control panel



The prompt Command: `_line` Specify first point: which appears in the command window at the command line



Make sure Snap is on by either pressing the F9 key or the SNAP button in the status bar. <Snap on> will show in the command palette.

Move the mouse around the drawing area. The cursor's pick box will jump from point to point at 5 unit intervals. The position of the pick box will show as coordinate numbers in the status bar (left-hand end).

Move the mouse until the coordinate numbers show 60,240,0 and press the Pick button of the mouse (*left-click*).

Move the mouse until the coordinate numbers show 260,240,0 and *left-click*.

Move the mouse until the coordinate numbers show 260,110,0 and *left-click*.

Move the mouse until the coordinate numbers show 60,110,0 and *left-click*.

Move the mouse until the coordinate numbers show 60,240,0 and *left-click*.

Then press the Return button of the mouse (*right-click*).



### **Second example**

Close the drawing and open a new drawing

*Left-click* on the Line tool icon and *enter* figures as follows at each prompt of the command line sequence:

Command: `_line` Specify first point: *enter* 80,235 *right-click*

Specify next point or [Undo]: *enter* 275,235 *right-click*

Specify next point or [Undo]: *enter* 295,210 *right-click*


Specify next point or [Close/Undo]: *enter* 295,100 *right-click*

Specify next point or [Close/Undo]: *enter* 230,100 *right-click*

Specify next point or [Close/Undo]: *enter* 230,70 *right-click*

Specify next point or [Close/Undo]: *enter* 120,70 *right-click*

Specify next point or [Close/Undo]: *enter 120,100 right-click*  
 Specify next point or [Close/Undo]: *enter 55,100 right-click*  
 Specify next point or [Close/Undo]: *enter 55,210 right-click*  
 Specify next point or [Close/Undo]: *enter c (Close) right-click*




### **Third example**

Close the drawing and open a new acadiso.dwt window.

*Left-click* on the Line tool icon and *enter* figures as follows at each prompt of the command line sequence:

Command: *\_line* Specify first point: *enter 60,210 right-click*  
 Specify next point or [Undo]: *enter @50,0 right-click*  
 Specify next point or [Undo]: *enter @0,20 right-click*  
 Specify next point or [Close/Undo]: *enter @130,0 right-click*  
 Specify next point or [Close/Undo]: *enter @0,-20 right-click*  
 Specify next point or [Close/Undo]: *enter @50,0 right-click*  
 Specify next point or [Close/Undo]: *enter @0,—105 right-click*  
 Specify next point or [Close/Undo]: *enter @—50,0 right-click*  
 Specify next point or [Close/Undo]: *enter @0,-20 right-click*  
 Specify next point or [Close/Undo]: *enter @—130,0 right-click*  
 Specify next point or [Close/Undo]: *enter @0,20 right-click*  
 Specify next point or [Close/Undo]: *enter @—50,0 right-click*  
 Specify next point or [Close/Undo]: *enter c (Close) right-click*



#### Notes.


The figures typed at the keyboard determining the corners of the outlines in the above examples are two-dimensional (2D) x, y coordinate points. When working in 2D, coordinates are expressed in terms of two numbers separated by a comma.

Coordinate points can be shown as positive or negative numbers.

The method of constructing an outline as shown in the first two examples is known as the absolute coordinate entry method, where the x, y coordinates of each corner of the outlines are entered at the command line as required.

The method of constructing an outline as in the third example is known as the relative coordinate entry method - coordinate points are entered relative to the previous entry. In relative coordinate entry, the @ symbol is entered before each set of coordinates with the following rules in mind:

The next example (the fourth) shows how lines at angles can be drawn taking advantage of the relative coordinate entry method. Angles in AutoCAD are measured in 360 degrees in a counter-clockwise (anticlockwise) direction. The < symbol precedes the angle.




#### **Fourth example**

*Left-click* on the Line tool icon and *enter* figures as follows at each prompt of the command line sequence:


Command: `_line` Specify first point: `70,230`  
 Specify next point: `@220,0`  
 Specify next point: `@0,—70`  
 Specify next point or [Undo]: `@115 < 225`  
 Specify next point or [Undo]: `@ —60,0`  
 Specify next point or [Close/Undo]: `@115 < 135`  
 Specify next point or [Close/Undo]: `@0,70`  
 Specify next point or [Close/Undo]: `c` (Close)

#### **Fifth example**

Another method of constructing accurate drawings is by using a method known as tracking. When Line is in use, as each Specify next point: appears at the command line, a *rubber-banded* line appears from the last point *entered*. *Drag* the rubber-band line in any direction and *enter* a number at the keyboard, followed by a *right-click*. The line is drawn in the *dragged* direction of a length in units equal to the *entered* number.



In this example because all lines are drawn in either the vertical or the horizontal direction, either press the **F8** key or *click* the **ORTHO** button in the status bar.



*Left-click* on the Line tool icon and *enter* figures as follows at each prompt of the command line sequence:


- Command: `_line` Specify first point: *enter*  $65,220$  *right-click*
- Specify next point: *drag* to right *enter*  $240$  *right-click*
- Specify next point: *drag* down *enter*  $145$  *right-click*
- Specify next point or [Undo]: *drag* left *enter*  $65$  *right-click*
- Specify next point or [Undo]: *drag* upwards *enter*  $25$  *right-click*
- Specify next point or [Close/Undo]: *drag* left *enter*  $120$  *right-click*

Specify next point or [Close/Undo]: *drag upwards enter 25 right-click*  
 Specify next point or [Close/Undo]: *drag left enter 55 right-click*  
 Specify next point or [Close/Undo]: *c (Close) right-click*

## Draw Circles


To create circles, you can specify various combinations of center, radius, diameter, points on the circumference, and points on other objects.

You can create circles in several ways. The default method is to specify the center and the radius. Three other ways to draw a circle are shown in the illustration.



### Draw a Circle Tangent to Other Objects

The tangent point is a point where an object touches another object without intersecting it. To create a circle that is tangent to other objects, select the objects and then specify the radius of the circle. In the illustrations below, the bold circle is the one being drawn, and points 1 and 2 select the objects to which it is tangent.



To create a circle tangent at three points, set running object snaps (OSNAP) to Tangent and use the three-point method to create the circle.

### Using CIRCLE command

Toolbar: Draw 

Menu: Draw > Circle

**Command entry:** *circle*

*Specify center point for circle or [3P/2P/Ttr (tan tan radius)]:* Specify a point or

enter an option


### **Center Point**

Draws a circle based on a center point and a diameter or a radius.

*Specify radius of circle or [Diameter]:* Specify a point, enter a value, enter d, or press ENTER

### **Radius**


Defines the radius of the circle. Enter a value, or specify a point (2). The distance between this point and the center point determines the radius of the circle.



### **Diameter**

Draws a circle using the center point and a specified distance for the diameter.

*Specify diameter of circle <current>:* Specify a point (2), enter a value, or press ENTER




### **3P (Three Points)**

Draws a circle based on three points on the circumference.

*Specify first point on circle:* Specify a point (1)

*Specify second point on circle:* Specify a point (2)

*Specify third point on circle:* Specify a point (3)




### **2P (Two Points)**

Draws a circle based on two endpoints of the diameter.

*Specify first endpoint of circle's diameter:* Specify a point (1)

*Specify second endpoint of circle's diameter:* Specify a point (2)






**TTR (Tangent, Tangent, Radius)**

Draws a circle with a specified radius tangent to two objects.

*Specify point on object for first tangent of circle:* Select a circle, arc, or line

*Specify point on object for second tangent of circle:* Select a circle, arc, or line

*Specify radius of circle <current>:*




Sometimes more than one circle matches the specified criteria. The program draws the circle of the specified radius whose tangent points are closest to the selected points.



**Drawing with the Circle tool examples**

Left-click on the Circle tool icon in the 2D Draw control panel




Enter numbers against the prompts appearing in the command window as shown

```
Command: _circle Specify center point for circle or [3P/2P/Ttr (tan tan radius)]: 180,160
Specify radius of circle or [Diameter]: 55
Command:
```

The circle appears on screen

### **Second example**

*Left-click* on the Circle tool icon and construct two circles (radius 50) as shown in the drawing



*Click* the Circle tool again and against the first prompt *enter t* (the abbreviation for the prompt *tan tan radius*), followed by a *right-click*.

Command: `_circle` Specify center point for circle or [3P/2P/Ttr (tan tan radius)]: *enter t right-click*


Specify point on object for first tangent of circle: *pick*

Specify point on object for second tangent of circle: *pick*

Specify radius of circle (50): *enter 40 right-click*

When a point on either circle is picked the Deferred Tangent tip appears. This tip will only appear when the OSNAP button is set on with a *click* on its button in the status bar, or by pressing the F3 key of the keyboard.

Circles can be drawn through 3 points or 2 points *entered* at the command line in response to prompts brought to the command line by using 3P and 2P in answer to the circle command line prompts




### Draw Arcs

To create an arc, you can specify various combinations of center, endpoint, start point, radius, angle, chord length, and direction values.

You can create arcs in several ways. With the exception of the first method, arcs are drawn counterclockwise from the start point to the endpoint.



#### Draw Arcs by Specifying Three Points

You can draw an arc by specifying three points. In the following example, the start point of the arc snaps to the endpoint of a line. The second point of the arc snaps to the middle circle in the illustration.



#### Draw Arcs by Specifying Start, Center, End

When you know the start point, center point, and endpoint, you can draw an arc by specifying either the start point or the center point first. The center point is the center of a circle that the arc is part of.




#### Draw Arcs by Specifying Start, Center, Angle

When you have a start point and a center point you can snap to and you know the included angle, use the Start, Center, Angle or the Center, Start, Angle option.




The included angle determines the endpoint of the arc. Use the Start, End, Angle method when you know both endpoints but cannot snap to a center point.



### Draw Arcs by Specifying Start, Center, Length

When you have a start point and a center point you can snap to; when you know the chord length, use the Start, Center, Length or the Center, Start, Length option.




The length of the chord of the arc determines the included angle.

### Draw Arcs by Specifying Start, End, Direction/Radius

When you have a start point and an endpoint, use the Start, End, Direction or the Start, End, Radius option.

The illustration on the left shows an arc drawn by specifying a start point, endpoint, and radius. You can specify the radius by entering a length or by moving the pointing device clockwise or counterclockwise and clicking to specify a distance.



The illustration on the right shows an arc drawn with the pointing device by specifying a start point and an endpoint and a direction. Moving the cursor up from the start point and endpoint draws the arc concave to the object, as shown here. Moving the cursor down draws the arc convex to the object.

### Draw Contiguous Arcs and Lines

Immediately after you complete an arc, you can start a line tangent to the arc at an endpoint by starting the LINE command and pressing ENTER at the Specify First Point prompt. You need to specify only the line length.



Conversely, after you complete a line, you can start an arc tangent to the line at an endpoint by starting the ARC command and pressing ENTER at the Specify Start Point prompt. You need to specify only the endpoint of the arc.



You can connect sequentially drawn arcs in the same way. To create connected arcs using a menu, click Draw menu > Arc > Continue. In both cases, the resulting object is tangent to the previous one. You can use the shortcut menu to repeat the Continue option.

### **Drawing with the Arc tool examples**


In AutoCAD 2008, arcs can be constructed using any three of the following characteristics of an arc: its Start point; a point on the arc (Second point); its Center; its End; its Radius; Length of the arc; Direction in which the arc is to be constructed; Angle between lines of the arc.

In the examples which follow, *entering* initials for these characteristics in response to prompts at the command line when the Arc tool is called allows arcs to be constructed in a variety of ways.

To call the Arc tool *click* on its tool icon in the 2D Draw control panel or *click* on Arc in the Draw drop-down menu. A sub-menu shows the possible methods of constructing arcs. The abbreviation for calling the Arc tool is a.




Left-click the Arc tool icon. The command line shows:  
 Command: \_arc Specify start point of arc or [Center]: 100,220  
 Specify second point of arc or [Center/End]: 55,250  
 Specify end point of arc: 10,220  
 Command:



### **Second example**


Command: *right-click* brings back the Arc sequence

ARC Specify start point of arc or [Center]: c (Center)  
Specify center point of arc: 200,190  
Specify start point of arc: 260,215  
Specify end point of arc or [Angle/chord Length]: 140,215  
Command:




### **Third example**

Command: *right-click* brings back the Arc sequence  
ARC Specify start point of arc or [Center]: 420,210  
Specify second point of arc or [Center/End]: e (End)  
Specify end point of arc: 320,210  
Specify center point of arc or [Angle/Direction/Radius]: r (Radius)  
Specify radius of arc: 75  
Command:



### **Draw Polylines**

A polyline is a connected sequence of line segments created as a single object. You can create straight line segments, arc segments, or a combination of the two.



Multisegmented lines provide editing capabilities unavailable for single lines. For example, you can adjust their width and curvature. After you've created a polyline, you can edit it with PEDIT or use EXPLODE to convert it to individual line and arc segments. You can

- Convert a spline-fit polyline into a true spline with SPLINE
- Use closed polylines to create a polygon

- Create a polyline from the boundaries of overlapping objects

### Create Arc Polylines

When you draw arc segments in a polyline, the first point of the arc is the endpoint of the previous segment. You can specify the angle, center point, direction, or radius of the arc. You can also complete the arc by specifying a second point and an endpoint.

### Create Closed Polylines

You can draw a closed polyline to create a polygon. To close a polyline, specify the starting point of the last side of the object, enter c (Close), and press ENTER.

### Create Wide Polylines

You can draw polylines of various widths by using the Width and Halfwidth options. You can set the width of individual segments and make them taper gradually from one width to another. These options become available after you specify a starting point for the polyline.



The Width and Halfwidth options set the width of the next polyline segments you draw. Zero (0) width produces a thin line. Widths greater than zero produce wide lines, which are filled if Fill mode is on and outlined if Fill mode is off. The Halfwidth option sets width by specifying the distance from the center of the wide polyline to an outside edge.

### Taper


When you use the Width option, you are prompted for both a starting and an ending width. By entering different values, you can taper the polyline. The starting and ending points of wide polyline segments are in the center of the line. Intersections of adjacent wide segments are usually beveled. However, nontangent arc segments, acute angles, or segments that use a dash-dot linetype are not beveled.

### Create Polylines from the Boundaries of Objects

You can create a polyline from the boundaries of overlapping objects that form a closed area. A polyline created using the boundary method is a separate object, distinct from the objects used to create it. You can edit it using the same methods used to edit other polylines.

To expedite the boundary selection process in large or complex drawings, you can specify a group of boundary candidates, called a boundary set. You create this set by selecting the objects you want to use define the boundary.






### Drawing with the Polyline tool examples

When drawing lines with the Line tool, each line drawn is an object in its own right. A rectangle drawn with the Line tool is four objects. A rectangle drawn with the Polyline tool is a single object. Lines of different thickness, arcs, arrows and circles can all be drawn using this tool as will be shown in the examples describing constructions using the Polyline tool. Constructions resulting from using the tool are known as polylines or plines.

The Polyline tool can be called from the 2D Draw control panel or from the Draw toolbar



*Left-click* the Polyline tool. The command line shows (In this example *enter* and *right-click* have not been included)

Command: `_pline` Specify start point: 30,250

Current line width is 0


Specify next point or [Arc/Halfwidth/Length/Undo/Width]: 230,250

Specify next point or [Arc/Close/Halfwidth/Length/Undo/Width]: 230,120

Specify next point or [Arc/Close/Halfwidth/Length/Undo/Width]: 30,120

Specify next point or [Arc/Close/Halfwidth/Length/Undo/Width]: c (Close)

Note the prompts – Arc for constructing pline arcs; Close to close an outline; Halfwidth to halve the width of a wide pline; Length to *enter* the required length of a pline; Undo to undo the last pline constructed; Close to close an outline.



Only the capital letter(s) of a prompt needs to be *entered* in upper or lower case to make that prompt effective.

Only the capital letter(s) of a prompt needs to be *entered* in upper or lower case to make that prompt effective.

Other prompts will appear when the Polyline tool is in use as will be shown in later examples.

### **Second example**

This will be a long sequence, but it is typical of a reasonably complex drawing using the Polyline tool. In the following sequences, when a prompt line is to be repeated, the prompts in square brackets ([ ]) will be replaced by [prompts].

*Left-click* the Polyline tool icon. The command line shows:

Command: `_pline` Specify start point: 40,250

Current line width is 0

Specify next point or [Arc/Halfwidth/Length/Undo/Width]: w (Width)

Specify starting width <0>: 5

Specify ending width <5>: *right-click*

Specify next point or [Arc/Close/Halfwidth/Length/Undo/Width]: 160,250

Specify next point or [prompts]: h (Halfwidth)

Specify starting half-width <2.5>: 1

Specify ending half-width <1>: *right-click*

Specify next point or [prompts]: 260,250

Specify next point or [prompts]: 260,180

Specify next point or [prompts]: w (Width)

Specify starting width <1>: 10

Specify ending width <10>: *right-click*

Specify next point or [prompts]: 260,120

Specify next point or [prompts]: h (Halfwidth)

Specify starting half-width <5>: 2

Specify ending half-width <2>: *right-click*

Specify next point or [prompts]: 160,120  
 Specify next point or [prompts]: w (Width)  
 Specify starting width <4>: 20  
 Specify ending width <20>: *right-click*  
 Specify next point or [prompts]: 40,120  
 Specify starting width <20>: 5  
 Specify ending width <5>: *right-click*  
 Specify next point or [prompts]: c (Close)




### ***Third example***

*Left-click* the Polyline tool icon. The command line shows:

Command: `_pline` Specify start point: 50,220  
 Current line width is 0  
 [prompts]: w (Width)  
 Specify starting width <0>: 0.5  
 Specify ending width <0.5>: *right-click*  
 Specify next point or [prompts]: 120,220  
 Specify next point or [prompts]: a (Arc)  
 Specify endpoint of arc or [prompts]: s (second pt)  
 Specify second point on arc: 150,200  
 Specify end point of arc: 180,220  
 Specify end point of arc or [prompts]: l (Line)  
 Specify next point or [prompts]: 250,220  
 Specify next point or [prompts]: 250,190  
 Specify next point or [prompts]: a (Arc)  
 Specify endpoint of arc or [prompts]: s (second pt)  
 Specify second point on arc: 240,170  
 Specify end point of arc: 250,150  
 Specify end point of arc or [prompts]: l (Line)  
 Specify next point or [prompts]: 250,150

Specify next point or [prompts]: 250,120

And so on until the outline in the picture is completed.



#### **Fourth example**

*Left-click* the Polyline tool icon. The command line shows:

Command: `_pline` Specify start point: 80,170

Current line width is 0

Specify next point or [prompts]: w (Width)

Specify starting width <0>: 1

Specify ending width <1>: *right-click*

Specify next point or [prompts]: a (Arc)


Specify endpoint of arc or [prompts]: s (second pt)

Specify second point on arc: 160,250

Specify end point of arc: 240,170

Specify end point of arc or [prompts]: cl (CLose)

The circle in the picture is formed



### **Fifth example**

*Left-click* the Polyline tool icon. The command line shows:

Command: `_pline` Specify start point: 60,180

Current line width is 0

Specify next point or [prompts]: w (Width)

Specify starting width <0>: 1

Specify ending width <1>: *right-click*

Specify next point or [prompts]: 190,180

Specify next point or [prompts]: w (Width)

Specify starting width <1>: 20

Specify ending width <20>: 0

Specify next point or [prompts]: 265,180

Specify next point or [prompts]: *right-click*


The arrow in the picture is formed.




## **Lecture #4. Creation of AutoCAD entities. Part 2**

### **Draw Ellipses**


The shape of an ellipse is determined by two axes that define its length and width. The longer axis is called the major axis, and the shorter one is the minor axis.



The illustrations below show two different ellipses created by specifying axis and distance. The third point specifies only a distance and does not necessarily designate the axis endpoint.



first axis as major axis




first axis as minor axis


If you are drawing on isometric planes to simulate 3D, you can use ellipses to represent isometric circles viewed from an oblique angle. First you need to turn on Isometric Snap in the Drafting Settings dialog box.

### Drawing with the Ellipse tool examples

Ellipses can be regarded as what is seen when a circle is viewed from directly in front of the circle and the circle rotated through an angle about its horizontal diameter. Ellipses are measured in terms of two axes - a major axis and a minor axis, the major axis being the diameter of the circle, the minor axis being the height of the ellipse after the circle has been rotated through an angle.




To call the Ellipse tool, *click on* its tool icon in the 2D Draw control panel or *click* on its name in the Draw drop-down menu. The abbreviation for calling the Ellipse tool is el.



*Left-click* the Ellipse tool icon. The command line shows:  
Command: `_ellipse`

Specify axis endpoint of elliptical arc or [Center]: 30,190  
Specify other endpoint of axis: 150,190  
Specify distance to other axis or [Rotation]: 25

Command:



### Second example

In this second example, the coordinates of the centre of the ellipse (the point where the two axes intersect) are *entered*, followed by *entering* coordinates for the end of the major axis, followed by *entering* the units for the end of the minor axis.

Command: *right-click*

ELLIPSE

Specify axis endpoint of elliptical arc or [Center]: c

Specify center of ellipse: 260,190

Specify endpoint of axis: 205,190

Specify distance to other axis or [Rotation]: 30

Command:



### Third example

Command: right-click

ELLIPSE


Specify axis endpoint of elliptical arc or [Center]: 30,100

Specify other endpoint of axis: 120,100

Specify distance to other axis or [Rotation]: r (Rotation)

Specify rotation around major axis: 45

Command:



### Draw Rectangles

Use RECTANG command to create closed polylines in a rectangular shape. You can specify the length, width, area, and rotation parameters. You can also control the type of corners on the rectangle—fillet, chamfer, or square.


Toolbar: Draw 

Menu: Draw ► RectangleAt the Command prompt, enter `rectang`.

Command entry: `rectang` or `rectangle`

### Drawing with the Rectangle tool examples

Call the Rectangle tool - either, with a *click* on its tool icon in the 2D Draw control panel, or by *entering* `rec` or `rectangle` at the command line.



The tool can be called from the Draw drop-down menu.

The command line shows:

Command: `_rectang`

Specify first corner point or [Chamfer/Elevation/Fillet/Thickness/ Width]:  
25,240

Specify other corner point or [Area/Dimensions/Rotation]:

160,160

Command:

25,240



160,160

Command: `_rectang`

[prompts]: `c` (Chamfer)

Specify first chamfer distance for rectangles `<0>`: 15


Specify first chamfer distance for rectangles `<15>`: *right-click*

Specify first corner point: 200,240

Specify other corner point: 300,160



Command:



Command: `_rectang`

Specify first corner point or [Chamfer/Elevation/Fillet/Thickness/Width]: w  
(Width)

Specify line width for rectangles <0>: 4

Specify first corner point or [Chamfer/Elevation/Fillet/Thickness/ Width]: c  
(Chamfer)


Specify first chamfer distance for rectangles <0>: 10

Specify second chamfer distance for rectangles <10>: 15

Specify first corner point or [Chamfer/Elevation/Fillet/Thickness/ Width]:  
200,120


Specify other corner point or [Area/Dimensions/Rotation]: 315,25

Command:




### Draw Regular Polygons

Use POLYGON command to create closed polylines with between 3 and 1,024 equal-length sides. The following illustrations show polygons created using three methods. In each case, two points are specified.




### Drawing with the Polygon tool examples

Call the Polygon tool - either with a *click* on its tool icon in the 2D Draw control panel, by *entering* pol or polygon at the command line.



It can be called from the Draw drop-down menu.



The command line shows  
 Command: \_polygon Enter number of sides <4>: 6  
 Specify center of polygon or [Edge]: 60,210

Enter an option [Inscribed in circle/Circumscribed about circle] <I>: *right-click*  
(accept Inscribed)

Specify radius of circle: 60

Command:


In the same manner construct a 5-sided polygon of centre 200,210 and of radius 60.

Then, construct an 8-sided polygon of centre 330,210 and radius 60.

Repeat to construct a 9-sided polygon circumscribed about a circle of radius 60 and centre 60,80.

Construct yet another polygon with 10 sides of radius 60 and of centre 200,80.


Finally another polygon circumscribing a circle of radius 60, of centre 330,80 and sides 12.



### Draw Donuts


Donuts are filled rings or solid-filled circles that actually are closed polylines with width.

To create a donut, you specify its inside and outside diameters and its center. You can continue creating multiple copies with the same diameter by specifying different center points. To create solid-filled circles, specify an inside diameter of 0.



To create a donut

1. Click Draw menu > Donut. At the Command prompt, enter donut.
2. Specify the inside diameter (1).
3. Specify the outside diameter (2).
4. Specify the center of the donut (3).
5. Specify the center point for another donut, or press ENTER to complete the command.



## Lecture #5. Editing the AutoCAD entities

### Modify Objects

You can easily modify the size, shape, and location of objects. You can

- Enter a command first, and then select the objects to modify.
- Select the objects first, and then enter a command to modify them.
- Select and right-click an object to display a shortcut menu with relevant options.
- Double-click an object to display the Properties palette or, in some cases, a dialog box or editor that is specific to that type of object. (You can specify the double click action for each object type by customizing a CUI file and loading it into the program.)

### Select Objects

You have a wide range of options when you need to select objects for editing operations.

#### Select Objects Individually

At the Select Objects prompt, you can select one or more objects individually.


*Use the Pickbox Cursor*

When the square pickbox cursor is in position to select an object, the object is highlighted. Click to select the object.

You can control the size of the pickbox in the Options dialog box, Selection tab.

### *Select Objects Close Together*

It is difficult to select objects that are close together or lie directly on top of one another. The example shows two lines and a circle that lie within the pickbox.



If selection preview is turned on, you can cycle through the objects by rolling over the object on top to highlight it, and pressing and holding SHIFT and then pressing SPACEBAR continuously. When the required object is highlighted, left-click to select it.

If selection preview is turned off, hold down SHIFT + SPACEBAR and click to cycle through these objects, one after the other, until the one you want is selected. Press ESC to turn off cycling.

### *Remove Selection from Objects*

Remove objects from the current selection set by holding down SHIFT and selecting them again.

## Select Multiple Objects


At the Select Objects prompt, you can select many objects at the same time.

### *Specify a Rectangular Selection Area*


Specify opposite corners to define a rectangular area. The background inside the area changes color and becomes transparent. The direction that you drag your cursor from the first point to the opposite corner determines which objects are selected.

- Window selection. Drag your cursor from left to right to select only objects that are entirely enclosed by the rectangular area.
- Crossing selection. Drag your cursor from right to left to select objects that the rectangular window encloses or crosses.

With a window selection, usually the entire object must be contained in the rectangular selection area. However, if an object with a noncontinuous (dashed) linetype is only partially visible in the viewport and all the visible vectors of the linetype can be enclosed within the selection window, the entire object is selected.




objects selected using window selection box




objects selected using crossing selection box

### Specify an Irregularly Shaped Selection Area

Specify points to define an irregularly shaped area. Use window polygon selection to select objects entirely enclosed by the selection area. Use crossing polygon selection to select objects enclosed or crossed by the selection area.




window polygon




result

### Specify a Selection Fence

In a complex drawing, use a selection fence. A selection fence looks like a polyline and selects only the objects it passes through. The circuit board illustration shows a fence selecting several components.



fence selection



selected objects highlighted

### Use Other Selection Options

You can see all selection options by entering ? at the Select Objects prompt. For a description of each of the selection options, see SELECT.

### Remove Selection from Multiple Objects

You can enter r (Remove) at the Select Objects prompt and use any selection option to remove objects from the selection set. If you are using the Remove option and want to return to adding objects to the selection set, enter a (Add).

You can also remove objects from the current selection set by holding down SHIFT and selecting them again, or by holding down SHIFT and then clicking and dragging window or crossing selections. You can add and remove objects repeatedly from the selection set.

## Correct Mistakes

You can backtrack your recent actions using one of several methods.

### *Undo a Single Action*

The simplest method of backtracking is to use Undo on the Standard toolbar or the U command to undo a single action. Many commands include their own U (undo) option so that you can correct mistakes without leaving the command. When you are creating lines and polylines, for example, enter u to undo the last segment.

*Note.* By default, the UNDO command is set to combine consecutive pan and zoom commands into a single operation when you undo or redo. However, pan and zoom commands that are started from the menu are not combined, and always remain separate actions.

### *Undo Several Actions at Once*

Use the Mark option of UNDO to mark an action as you work. You can then use the Back option of UNDO to undo all actions that occurred after the marked action. Use the Begin and End options of UNDO to define a set of actions to be treated as a group.

You can also undo several actions at once with the Undo list on the Standard toolbar.

### *Reverse the Effect of Undo*

You can reverse the effect of a single U or UNDO command by using REDO immediately after using U or UNDO.

You can also redo several actions at once with the Redo list on the Standard toolbar.

### *Erase Objects*

You can erase any object that you draw. If you accidentally erase the wrong object, you can use the UNDO command or the OOPS command to restore it.

### *Cancel a Command*

You can cancel a command without completing it by pressing ESC.

## Erase Objects

You can erase objects from your drawing using several methods.

- Erase them with ERASE.
- Select them and then cut them to the Clipboard with CTRL+X.
- Select them and press DELETE.

You can restore accidentally erased objects using UNDO. The OOPS command restores all objects deleted by the most recent use of ERASE.

Toolbar: Modify 

Menu: Modify ► Erase

Shortcut menu: Select the objects to erase, right-click in the drawing area, and click Erase.

Command entry: erase

### *Clean Up the Display*

You can remove the plus-shaped markers called blips and stray pixels that may be left over from some editing operations from the display area.

- To remove blips, use REDRAW.
- To remove stray pixels, use REGEN.

## Move Objects

You can move objects at a specified distance and direction from the originals.

Use coordinates, grid snap, object snaps, and other tools to move objects with precision.

Toolbar: Modify 


Menu: Modify ► Move

Shortcut menu: Select the objects to move, and right-click in the drawing area. Click Move.

Command entry: move

### Specify Distance with Two Points

Move an object using the distance and direction specified by a base point followed by a second point. In this example, you move the block representing a window. Click Edit menu ► Move. Then select the object to be moved (1). Specify the base point for the move (2) followed by a second point (3). The object is moved the distance and direction of point 2 to point 3.



### Specify Distance with Relative Coordinates

You can move an object using a relative distance by entering coordinate values for the first point and pressing ENTER for the second point. The coordinate values are used as a relative displacement rather than the location of a base point.

Note. Do not include an @ sign as you normally would for relative coordinates, because relative coordinates are expected.




To copy objects a specified distance, you can also use direct distance entry with Ortho mode and polar tracking. For more information, see Enter Direct Distances

#### *Use a Stretch-Move*

You can also use STRETCH to move objects if all their endpoints lie entirely within the selection window. Turn on Ortho mode or polar tracking to move the objects at a specific angle.

A practical example is moving a door in a wall. The door in the illustration is entirely within a crossing selection, while the wall lines are only partly within the crossing selection area.



The result is that only the endpoints that lie within the crossing selection move.

## **Rotate Objects**

You can rotate objects in your drawing around a specified base point.

To determine the angle of rotation, you can enter an angle value, drag using the cursor, or specify a reference angle to align to an absolute angle.



Toolbar: Modify

Menu: Modify ► Rotate

Shortcut menu: Select the objects to rotate, and right-click in the drawing area. Click Rotate.

Command entry: rotate


#### *Rotate an Object by a Specified Angle*

Enter a rotation angle value from 0 to 360 degrees. You can also enter values in radians, grads, or surveyor bearings. Entering a positive angle value rotates the objects counterclockwise or clockwise, depending on the Direction Control setting in the Drawing Units dialog box.

#### *Rotate an Object by Dragging*

Drag the object around the base point and specify a second point. Use Ortho mode, polar tracking, or object snaps for greater precision.


For example, you can rotate the plan view of a house by selecting the objects (1), specifying a base point (2), and specifying an angle of rotation by dragging to another point (3).



### Rotate an Object to an Absolute Angle

With the Reference option, you can rotate an object to align it to an absolute angle.

For example, to rotate the part in the illustration so the diagonal edge rotates to 90 degrees, you select the objects to be rotated (1, 2), specify the base point (3), and enter the Reference option. For the reference angle, specify the two endpoints of the diagonal line (4, 5). For the new angle, enter 90.



### Scale Objects

You can enlarge or reduce selected objects proportionally in the X, Y, and Z directions

Toolbar: Modify 

Menu: Modify ► Scale

Shortcut menu: Select the objects to scale, and right-click in the drawing area. Click Scale.


Command entry: scale

#### *Scale Objects Using a Scale Factor*

With SCALE, you can make an object uniformly larger or smaller. To scale an object, you specify a base point and a scale factor. Alternatively, you can specify a length to be used as a scale factor based on the current drawing units.

A scale factor greater than 1 enlarges the object. A scale factor between 0 and 1 shrinks the object.

Scaling changes the size of all dimensions of the selected object. A scale factor greater than 1 enlarges the object. A scale factor less than 1 shrinks the object.



*Note.* When you use the SCALE command with annotative objects, the position or location of the object is scaled relative to the base point of the scale operation, but the size of the object is not changed.

#### *Scale Objects Using a Reference Distance*

You can also scale by reference. Scaling by reference uses an existing distance as a basis for the new size. To scale by reference, specify the current distance and then the new desired size. For example, if one side of an object is 4.8 units long and you want to expand it to 7.5 units, use 4.8 as the reference length.

You can use the Reference option to scale an entire drawing. For example, use this option when the original drawing units need to be changed. Select all objects in the drawing. Then use Reference to select two points and specify the intended distance. All the objects in the drawing are scaled accordingly.

## **Copy Objects**

You can create duplicates of objects at a specified distance and direction from the originals.

Use coordinates, grid snap, object snaps, and other tools to copy objects with precision.



Toolbar: Modify


Menu: Modify ► Copy

Shortcut menu: Select the objects to copy, and right-click in the drawing area. Click Copy Selection.

Command entry: copy

#### *Specify Distance with Two Points*

Copy an object using the distance and direction specified by a base point followed by a second point. In this example, you copy the block representing an electronic component. Click Edit menu ► Copy. At the Command prompt, enter copyclip. Then select the original object to be copied. Specify the base point for the move (1) followed by a second point (2). The object is copied the distance and direction of point 1 to point 2.



### Specify Distance with Relative Coordinates


Copy an object using a relative distance by entering coordinate values for the first point and pressing ENTER for the second point. The coordinate values are used as a relative displacement rather than the location of a base point.

Note. **Do not include an @ sign as you normally would for relative coordinates, because relative coordinates are expected.**

To copy objects a specified distance, you can also use direct distance entry with Ortho mode and polar tracking. For more information, see Enter Direct Distances.

### Create Multiple Copies


The COPY command repeats automatically by default. To exit the command, press ENTER. To change the default, use the COPYMODE system variable.



## Mirror Objects

You can flip objects about a specified axis to create a symmetrical mirror image.


Mirroring is useful for creating symmetrical objects because you can quickly draw half the object and then mirror it instead of drawing the entire object.

Toolbar: Modify 

Menu: Modify ► Mirror

Command entry: mirror

You flip objects about an axis called a mirror line to create a mirror image. To specify this temporary mirror line, you enter two points. You can choose whether to erase or retain the original objects.



By default, when you mirror text, attributes, and attribute definitions, they are not reversed or turned upside down in the mirror image. The text has the same alignment and justification as before the object was mirrored. If you do want text to be reversed, set the MIRRTEXT system variable to 1.




MIRRTEXT affects text that is created with the TEXT, ATTDEF, or MTEXT commands; attribute definitions; and variable attributes. Text and constant attributes that are part of an inserted block are reversed when the block is mirrored regardless of the MIRRTEXT setting.


### Create an Array of Objects

You can create copies of objects in a rectangular or polar (circular) pattern called an array.


For rectangular arrays, you control the number of rows and columns and the distance between each.




A rectangular array is built along a baseline defined by the current snap rotation angle. This angle is zero by default, so the rows and columns of a rectangular array are orthogonal with respect to the X and Y axes. The default angle 0 direction setting can be changed in UNITS.



For polar arrays, you control the number of copies of the object and whether the copies are rotated. To create many regularly spaced objects, arraying is faster than copying.



Toolbar: Modify   
 Menu: Modify ► Array  
 Command entry: array

The Array dialog box is displayed. You can create rectangular or polar arrays by choosing the appropriate option. Each object in an array can be manipulated independently. If you select multiple objects, the objects are treated as one item to be copied and arrayed.

If you enter -array at the command prompt, options are displayed at the command prompt.

Use the Rectangular Array option to create an array of rows and columns of copies of the selected object. Use the Polar Array option to create an array by copying the selected objects around a center point.

Other options: Select Objects, Preview Area, Preview.

### Select Objects

Specifies the objects used to construct the array. You can select objects before or after the Array dialog box is displayed. To select objects when the Array dialog box is displayed, choose Select Objects. The dialog box temporarily closes. When you finish selecting objects, press ENTER. The Array dialog box is redisplayed, and the number of objects selected is shown below the Select Objects button.



*Note.* If you select multiple objects, the base point of the last selected object is used to construct the array.

#### Preview Area


Shows a preview image of the array based on the current settings in the dialog box. The preview image is dynamically updated when you move to another field after changing a setting.

#### Preview

Closes the Array dialog box and displays the array in the current drawing. Choose Modify to return to the Array dialog box to make changes.

### Rectangular Array

Creates an array of rows and columns of copies of the selected object.



**Rows** – specifies the number of rows in the array.

If you specify one row, you must specify more than one column. If you specify a large number of rows and columns for the array, it might take a while to create the copies. By default, the maximum number of array elements that you can generate in one command is 100,000. The limit is set by the MAXARRAY setting in the registry. To reset the limit to 200,000, for example, enter (setenv "MaxArray" "200000") at the Command prompt.

**Columns** – specifies the number of columns in the array.

If you specify one column, you must specify more than one row. If you specify a large number of rows and columns for the array, it might take a while to create the copies. By default, the maximum number of array elements that you can generate in

one command is 100,000. The limit is set by the MAXARRAY setting in the registry. To reset the limit to 200,000, for example, enter (setenv "MaxArray" "200000") at the Command prompt.

Offset Distance and Direction – provides a space for you to specify the distance and direction of the array's offset.

- Row Offset specifies the distance (in units) between rows. To add rows downward, specify a negative value. To specify row spacing with the pointing device, use the Pick Both Offsets button or the Pick Row Offset button.
- Column Offset specifies the distance (in units) between columns. To add columns to the left, specify a negative value. To specify column spacing with the pointing device, use the Pick Both Offsets button or the Pick Column Offset button.
- Angle of Array specifies the angle of rotation. This angle is normally 0, so the rows and columns are orthogonal with respect to the X and Y drawing axes of the current UCS. You can change the measurement conventions for angles using UNITS. The ANGBASE and ANGDIR system variables affect the angle of arrays.
- Pick Both Offsets temporarily closes the Array dialog box so that you can use the pointing device to set the row and column spacing by specifying two diagonal corners of a rectangle.
- Pick Row Offset temporarily closes the Array dialog box so that you can use the pointing device to specify the distance between rows. ARRAY prompts you to specify two points and uses the distance and direction between the points to specify the value in Row Offset.
- Pick Column Offset temporarily closes the Array dialog box so that you can use the pointing device to specify the distance between columns. ARRAY prompts you to specify two points and uses the distance and direction between the points to specify the value in Column Offset.
- Pick Angle of Array temporarily closes the Array dialog box so that you can specify the angle of rotation by entering a value or using the pointing device to specify two points. You can change the measurement conventions for angles using UNITS. The ANGBASE and ANGDIR system variables affect the angle of arrays.

### **Polar Array**

Creates an array by copying the selected objects around a specified center point.

#### *Center Point*

Specifies the center point of the polar array. Enter coordinate values for X and Y, or choose Pick Center Point to use the pointing device to specify the location.

#### *Pick Center Point*




Temporarily closes the Array dialog box so that you can use the pointing device to specify the center point in the drawing area.

### *Method and Values*

Specifies the method and values used to position objects in the polar array.

- Method sets the method used to position objects. This setting controls which of the Method and Value fields are available for specifying values. For example, if the method is Total Number of Items & Angle to Fill, the related fields are available for specifying values; the Angle Between Items field is not available.
- Total Number of Items sets the number of objects that appear in the resultant array. The default value is 4.
- Angle to Fill sets the size of the array by defining the included angle between the base points of the first and last elements in the array. A positive value specifies counterclockwise rotation. A negative value specifies clockwise rotation. The default value is 360. A value of 0 is not permitted.
- Angle Between Items sets the included angle between the base points of the arrayed objects and the center of the array. Enter a positive value. The default direction value is 90. You can choose the Pick buttons and use the pointing device to specify the values for Angle to Fill and Angle Between Items.



- Pick Angle to Fill temporarily closes the Array dialog box so that you can

define the included angle between the base points of the first and last elements in the array. ARRAY prompts you to select a point relative to another point in the drawing area.

- Pick Angle Between Items temporarily closes the Array dialog box so that you can define the included angle between the base points of the arrayed objects and the center of the array. ARRAY prompts you to select a point relative to another point in the drawing area.

#### Rotate Items as Copied

Rotates the items in the array, as shown in the preview area.

#### More/Less

Turns the display of additional options in the Array dialog box on and off. When you choose More, additional options are displayed, and the name of this button changes to Less.

#### Object Base Point

Specifies a new reference (base) point relative to the selected objects that will remain at a constant distance from the center point of the array as the objects are arrayed. To construct a polar array, ARRAY determines the distance from the array's center point to a reference (base) point on the last object selected. The point used depends on the type of object, as shown in the following table.

Object type	Default base point
Arc, circle, ellipse	Center point
Polygon, rectangle	First corner
Donut, line, polyline	Starting point

#### Set to Object's Default

Uses the default base point of the object to position the arrayed object. To manually set the base point, clear this option.

#### Base Point

Sets a new X and Y base point coordinate. Choose Pick Base Point to temporarily close the dialog box and specify a point. After you specify a point, the Array dialog box is redisplayed.

Note. To avoid unexpected results, set the base point manually if you are constructing a polar array and do not want to rotate the objects.

## Lecture #6.

### Changing the properties of the AutoCAD entities

#### Overview of Object Properties

Every object you draw has properties. Some properties are general and apply to most objects; for example, layer, color, linetype, and plot style. Other properties are

object-specific; for example, the properties of a circle include radius and area, and the properties of a line include length and angle.

Most general properties can be assigned to an object by layer or can be assigned to an object directly.

- When a property is set to the value `BYLAYER`, the object is assigned the same value as the layer on which it is drawn. For example, if a line drawn on Layer0 is assigned the color `BYLAYER`, and Layer0 is assigned the color Red, the line is red.
- When a property is set to a specific value, that value overrides the value set for the layer. For example, if a line drawn on Layer0 is assigned the color Blue, and Layer0 is assigned the color Red, the line is blue.

There are eight general properties common to all objects. All other object properties are specific to the type of object.

The following general properties are common to most objects and custom objects (third-party application objects based on AutoCAD API standards).

#### *Color*

Specifies the color for objects. Selecting `Select Color` in the color list displays the `Select Color` dialog box (see `COLOR`).

You can use the `Select Color` dialog box to define the color of objects by selecting from the 255 AutoCAD Color Index (ACI) colors, true colors, and color book colors.

#### *Layer*

Specifies the current layer of the object. The list shows all layers in the current drawing (see `LAYER`).

#### *Linetype*

Specifies the current linetype of the object. The list shows all linetypes in the current drawing (see `LINETYPE`).



#### *Linetype Scale*

Specifies the linetype scale factor of the object (see `LTSCALE`).

#### *Plot Style*

Lists `NORMAL`, `BYLAYER`, `BYBLOCK`, plus any plot styles contained in the current plot style table (see `PLOTSTYLE`).

#### *Lineweight*

Specifies the lineweight of the object. The list shows all available lineweights in the current drawing (see `LWEIGHT`).

#### *Hyperlink*

Attaches a hyperlink to a graphical object. If a description has been assigned to the hyperlink, the description is displayed. If no description has been assigned, the URL is displayed (see `HYPERLINK`).

#### *Thickness*

Sets the current 3D thickness. This property does not apply to all objects (see CHPROP).



The PROPERTIES command controls properties of existing objects




Toolbar: Standard

Menu: Modify ► Properties.

Shortcut menu: Select the objects whose properties you want to view or modify, right-click in the drawing area, and click Properties.

Command entry: properties

The Properties palette is displayed. The Properties palette lists properties of the selected object or set of objects.



You can also view or modify properties of third-party application objects that are based on AutoCAD application programming interface (API) standards.

The Properties palette lists the current settings for properties of the selected object or set of objects. You can modify any property that can be changed by specifying a new value.

- When more than one object is selected, the Properties palette displays only those properties common to all objects in the selection set.
- When no objects are selected, the Properties palette displays only the general

properties of the current layer, the name of the plot style table attached to the layer, the view properties, and information about the UCS.


You can double-click most objects to open the Properties palette when the DBLCLKEDIT system variable is on (the default). The exceptions include blocks and attributes, hatches, gradient fills, text, multilines, and xrefs. If you double-click any of these objects, an object-specific dialog box displays instead of the Properties palette.

## Copy Properties Between Objects

You can copy some or all properties of one object to other objects using Match Properties.

The types of properties that can be copied include, but are not limited to, color, layer, linetype, linetype scale, lineweight, plot style, viewport property overrides, and 3D thickness.

By default, all applicable properties are automatically copied from the first object you selected to the other objects. If you don't want a specific property or properties to be copied, use the Settings option to suppress the copying of that property. You can choose the Settings option at any time during the command.



The MATCHPROP command applies the properties of a selected object to other objects

Toolbar: Standard 

Menu: Modify ► Match Properties


Command entry: matchprop

Destination Object(s)

Specifies the objects to which you want to copy the properties of the source object. You can continue selecting destination objects, or press ENTER to apply the properties and end the command.

Settings

Displays the Property Settings dialog box, in which you can control which object properties to copy to the destination objects. By default, in the Property Settings dialog box all object properties are selected for copying.



Color changes the color of the destination object to that of the source object. Available for all objects.

Layer changes the layer of the destination object to that of the source object. Available for all objects.

*Linetype* changes the linetype of the destination object to that of the source object. Available for all objects except attributes, hatches, multiline text, points, and viewports.

*Linetype Scale* changes the linetype scale factor of the destination object to that of the source object. Available for all objects except attributes, hatches, multiline text, points, and viewports.

*Lineweight* changes the lineweight of the destination object to that of the source object. Available for all objects.

*Thickness* changes the thickness of the destination object to that of the source object. Available only for arcs, attributes, circles, lines, points, 2D polylines, regions, text, and traces.


*Plot Style* changes the plot style of the destination object to that of the source object. If you are working in color-dependent plot style mode (PSTYLEPOLICY is set to 1), this option is unavailable. Available for all objects, except those with the Jitter edge modifier applied.

*Polyline*. In addition to basic object properties, changes the width and linetype generation properties of the destination polyline to those of the source polyline. The fit/smooth property and the elevation of the source polyline are not transferred to the destination polyline. If the source polyline has variable width, the width property is not transferred to the destination polyline.


## Control the Display Properties of Certain Objects

### Turn Off Solid Fill

When you turn off Fill mode, wide polylines, solid-filled polygons, gradient fill, and hatches are displayed in outline form. Except for patterned hatches and gradient fills, solid fill is automatically turned off for hidden view and nonplan views in three dimensions.



Fill mode on




Fill mode off

### Use Quick Text


When you turn on Quick Text mode in drawings that contain a lot of text using complex fonts, only a rectangular frame defining the text is displayed or plotted.

### Turn Off Lineweights

Any lineweight width that is represented by more than one pixel may slow down performance. If you want to improve display performance, turn lineweights off. You can turn lineweights on and off by choosing the LWT button on the status bar or by using the Lineweight Settings dialog box. Lineweights are always plotted at their real-world value whether their display is turned on or off.



Quick Text mode off



Quick Text mode on

### Update the Display

New objects automatically use the current settings for displays of solid fill and text. Except for lineweights, to update the display of existing objects using these settings, you must use REGEN.


# Lecture #7.

## Geometrical constructing with the use of Object Snap.

### Use Precision Tools

You can use a variety of precision drawing tools to help you produce accurate drawings quickly and without performing tedious calculations.


You can use **Drafting Settings Dialog Box** that specifies drafting settings organized for drawing aids in four categories: Snap and Grid, Polar Tracking, Object Snap, and Dynamic Input.



Menu: Tools ► Drafting Settings

Shortcut menu: Right-click Snap, Grid, Polar, Osnap, Otrack, or Dyn on the status bar and click Settings.





Command entry: dsettings (or 'dsettings for transparent use)

## Snap and Grid

To enhance drawing speed and efficiency, you can display and snap to a rectangular grid. You can also control its spacing, angle, and alignment.


The grid is a rectangular pattern of dots or lines that extends over the area you specify as the grid limits. Using the grid is similar to placing a sheet of grid paper under a drawing. The grid helps you align objects and visualize the distances between them. The grid is not plotted.

Snap mode restricts the movement of the crosshairs to intervals that you define. When Snap mode is on, the cursor seems to adhere, or "snap," to an invisible rectangular grid. Snap is useful for specifying precise points with the arrow keys or the pointing device.

Grid mode and Snap mode are independent but are often turned on at the same time.

### *Control the Display Style and Area of the Grid*

You can display the grid either as a rectangular pattern of dots or as rectangular pattern of lines. The grid displays dots only when the current visual style is set to 2D Wireframe, otherwise the grid displays lines. A lined grid is displayed for all visual styles while working in 3D. There are several methods to change the current visual style, including the VSCURRENT command.



By default, the X and Y axes of the UCS display in a different color than the grid lines. You can control the color in the Drawing Window Colors dialog box. This dialog box is accessible from the Drafting tab in the Options dialog box.

The LIMITS command controls the drawing area covered by the grid. As an option, you can override the limits to make the grid cover the entire XY plane of the user coordinate system (UCS). You can access this option in the Drafting Settings dialog box or use the GRIDDISPLAY system variable.

*Note.* When you use dynamic UCS, the grid limits are set automatically relative to the size of the selected face of the solid and the drawing area available.


### *Control the Frequency of Major Grid Lines*

If the grid is displayed as lines rather than dots, darker lines called major grid lines display at intervals. When working in decimal units or with feet and inches, major grid lines are especially useful for measuring distances quickly. You can control the frequency of major grid lines in the Drafting Settings dialog box.

To turn off the display of major grid lines, set the frequency of major grid lines to 1.

*Note.* If the grid is displayed as lines, the grid limits are displayed also as darker lines. Do not confuse these boundaries with major grid lines.

*Note.* When the grid is displayed as lines and SNAPANG is set to a value other than 0, the grid will not display. SNAPANG does not affect the display of the dotted grid.



### *Change the Grid Dynamically During Zooming*

If you zoom in or out of your drawing, the grid spacing is adjusted automatically to be more appropriate for the new magnification. This is called adaptive grid display.

For example, if you zoom way out, the density of displayed grid lines reduces automatically. Conversely, if you zoom way in, additional grid lines display in the same proportion as the major grid lines.


### *Change Grid and Snap Spacing*

As you work, you can turn Grid and Snap mode on and off, and you can change the grid and snap spacing. You can turn Snap mode on and off temporarily by using an override key.

Snap spacing does not have to match grid spacing. For example, you might set a wide grid spacing to be used as a reference but maintain a closer snap spacing for accuracy in specifying points.

### *Change the Grid and Snap Angle and Base*

If you need to draw along a specific alignment or angle, you can change the grid and snap angle by rotating the user coordinate system (UCS). This rotation realigns the crosshairs on the screen to match the new angle. In the following example, the UCS is rotated 30 degrees to match the angle of the anchor bracket.



The grid and snap points are always aligned with the UCS origin. If you need to shift the grid and grid snap origin, move the UCS.

**Snap and Grid Tab** (Drafting Settings Dialog Box) specifies Snap and Grid settings.

#### Snap On

Turns Snap mode on or off. You can also turn Snap mode on or off by clicking Snap on the status bar, by pressing F9, or by using the SNAPMODE system variable.

#### Snap Spacing

Controls an invisible, rectangular grid of snap locations that restricts cursor movement to specified X and Y intervals.

*Snap X Spacing* specifies the snap spacing in the X direction. The value must be a positive real number. (SNAPUNIT system variable)

*Snap Y Spacing* specifies the snap spacing in the Y direction. The value must be a positive real number. (SNAPUNIT system variable)

*Equal X and Y Spacing* forces the X and Y spacing to the same values for snap spacing and for grid spacing. The snap spacing intervals can be different from the grid spacing intervals.

### Polar Spacing

Controls the PolarSnap increment distance.

*Polar Distance* sets the snap increment distance when PolarSnap is selected under Snap Type & Style. If this value is 0, the PolarSnap distance assumes the value for Snap X Spacing. The Polar Distance setting is used in conjunction with polar tracking and/or object snap tracking. If neither tracking feature is enabled, the Polar Distance setting has no effect. (POLARDIST system variable)

### Snap Type

Sets the snap style and snap type.

*Grid Snap* sets the snap type to Grid. When you specify points, the cursor snaps along vertical or horizontal grid points. (SNAPTYPE system variable)

*Rectangular Snap* sets the snap style to standard Rectangular snap mode. When the snap type is set to Grid snap and Snap mode is on, the cursor snaps to a rectangular snap grid. (SNAPSTYL system variable)

*Isometric Snap* sets the snap style to Isometric snap mode. When the snap type is set to Grid snap and Snap mode is on, the cursor snaps to an isometric snap grid. (SNAPSTYL system variable)

*PolarSnap* sets the snap type to Polar. When Snap mode is on and you specify points with polar tracking turned on, the cursor snaps along polar alignment angles set on the Polar Tracking tab relative to the starting polar tracking point. (SNAPTYPE system variable)

### Grid On

Turns the grid on or off. You can also turn grid mode on or off by clicking Grid on the status bar, by pressing F7, or by using the GRIDMODE system variable.

### Grid Spacing

Controls the display of a grid that helps you visualize distances.

*Note.* The limits of the grid are controlled by the LIMITS command and the GRIDDISPLAY system variable.

*Grid X Spacing* specifies the grid spacing in the X direction. If this value is 0, the grid assumes the value set for Snap X Spacing (GRIDUNIT system variable).

*Grid Y Spacing* specifies the grid spacing in the Y direction. If this value is 0, the grid assumes the value set for Snap Y Spacing (GRIDUNIT system variable).

*Major Line Every* specifies the frequency of major grid lines compared to minor grid lines. Grid lines rather than grid dots are displayed when the VSCURRENT is set to any visual style except 2D Wireframe (GRIDMAJOR system variable).

### Grid Behavior

Controls the appearance of the grid lines that are displayed when VSCURRENT is set to any visual style except 2D Wireframe.

*Adaptive Grid* limits the density of the grid when zoomed out. (GRIDDISPLAY system variable)

*Allow Subdivision Below Grid Spacing* generates additional, more closely spaced grid lines when zoomed in. The frequency of these grid lines is determined by the frequency of the major grid lines. (GRIDDISPLAY and GRIDMAJOR system variables)

*Display Grid Beyond Limits* displays the grid beyond the area specified by the LIMITS command. (GRIDDISPLAY system variable)

*Follow Dynamic UCS* changes the grid plane to follow the XY plane of the dynamic UCS. (GRIDDISPLAY system variable)


## Polar Tracking

Polar tracking restricts cursor movement to specified angles. PolarSnap restricts cursor movement to specified increments along a polar angle.

When you are creating or modifying objects, you can use polar tracking to display temporary alignment paths defined by the polar angles you specify. In 3D views, polar tracking additionally provides an alignment path in the up and down directions. In that case, the tooltip displays a +Z or -Z for the angle.

Polar angles are relative to the orientation of the current user coordinate system (UCS) and the setting for the base angle convention in a drawing. The angle base direction is set in the Drawing Units dialog box.

Use PolarSnap to snap to specified distances along the alignment path. For example, in the following illustration you draw a two-unit line from point 1 to point 2, and then draw a two-unit line to point 3 at a 45-degree angle to the line. If you turn on the 45-degree polar angle increment, an alignment path and tooltip are displayed when your cursor crosses the 0 or 45-degree angle. The alignment path and tooltip disappear when you move the cursor away from the angle.




As you move your cursor, alignment paths and tooltips are displayed when you move the cursor near polar angles. The default angle measurement is 90 degrees. Use the alignment path and tooltip to draw your object. You can use polar tracking with Intersection and Apparent Intersection object snaps to find where a polar alignment path intersects another object.

*Note.* Ortho mode and polar tracking cannot be on at the same time. Turning on polar tracking turns off Ortho mode. Similarly, PolarSnap and grid snap cannot be on at the same time. Turning on PolarSnap turns off grid snap.

### Specify Polar Angles (Polar Tracking)

You can use polar tracking to track along polar angle increments of 90, 60, 45, 30, 22.5, 18, 15, 10, and 5 degrees, or you can specify other angles. The following illustration shows the alignment paths displayed as you move your cursor 90 degrees with the polar angle increment set to 30 degrees.



The orientation of 0 depends on the angle you set in the Drawing Units dialog box (UNITS). The direction of snap (clockwise or counterclockwise) depends on the units direction you specify when setting units of measurement.

You can turn polar tracking on and off temporarily by using an override key. The direct distance entry method is not available while you are using the temporary override key for polar tracking.

### ***Specify Polar Distances (PolarSnap)***

PolarSnap restricts cursor movement to increments of a polar distance you specify. For example, if you specify a length of 4 units, the cursor snaps from the first point specified to lengths of 0, 4, 8, 12, 16, and so on. As you move your cursor, a tooltip indicates the nearest PolarSnap increment. To restrict point entry to polar distances, both polar tracking and Snap mode (set to PolarSnap) must be on. You can turn off all snapping and tracking temporarily by using an override key.

Polar Tracking Tab (Drafting Settings Dialog Box) controls the AutoTrack settings.

#### **Polar Tracking On**

Turns polar tracking on and off. You can also turn polar tracking on or off by pressing F10 or by using the AUTOSNAP system variable.

#### ***Polar Angle Settings***

Sets the alignment angles for polar tracking. (POLARANG system variable)

*Increment Angle* sets the polar increment angle used to display polar tracking alignment paths. You can enter any angle, or select a common angle of 90, 45, 30, 22.5, 18, 15, 10, or 5 degrees from the list. (POLARANG system variable)

*Additional Angles* makes any additional angles in the list available for polar tracking. The Additional Angles check box is also controlled by the POLARMODE system variable, and the list of additional angles is also controlled by the POLARADDANG system variable.

*Note.* Additional angles are absolute, not incremental.

*List of Angles* if Additional Angles is selected, lists the additional angles that are available. To add new angles, click New. To remove existing angles, click Delete. (POLARADDANG system variable)

*New* adds up to 10 additional polar tracking alignment angles.

*Note.* Before adding fractional angles, you must set the AUPREC system variable to the appropriate decimal precision to avoid undesired rounding. For example, if the value of AUPREC is 0 (the default value), all fractional angles you enter are rounded to the nearest whole number.

*Delete* deletes selected additional angles.

## Object Snap Tracking Settings

Sets options for object snap tracking.

*Track Orthogonally Only* displays only orthogonal (horizontal/vertical) object snap tracking paths for acquired object snap points when object snap tracking is on. (POLARMODE system variable)

*Track Using All Polar Angle Settings* applies polar tracking settings to object snap tracking. When you use object snap tracking, the cursor tracks along polar alignment angles from acquired object snap points. (POLARMODE system variable)

*Note.* Clicking Polar and Otrack on the status bar also turns polar tracking and object snap tracking on and off.

### Polar Angle Measurement

Sets the basis by which polar tracking alignment angles are measured.


*Absolute* bases polar tracking angles on the current user coordinate system (UCS).

*Relative to Last Segment* bases polar tracking angles on the last segment drawn.

## Object Snap

Use object snaps to specify precise locations on objects. For example, you can use an object snap to draw a line to the center of a circle or to the midpoint of a polyline segment.

You can specify an object snap whenever you are prompted for a point. By default, a marker and a tooltip are displayed when you move the cursor over an object snap location on an object. This feature, called AutoSnap™, provides a visual clue that indicates which object snaps are in effect.



### *Specify an Object Snap*

To specify an object snap at a prompt for a point, you can

- Press SHIFT and right-click to display the Object Snap shortcut menu.
- Click an object snap button on the Object Snap toolbar.
- Enter the name of an object snap at the command prompt.

When you specify an object snap at a prompt for a point, the object snap stays in effect only for the next point that you specify.

*Note.* Object snaps work only when you are prompted for a point. If you try to use an object snap at the Command prompt, an error message is displayed.

## Use Running Object Snaps

If you need to use one or more object snaps repeatedly, you can turn on running object snaps. For example, you might set Center as a running object snap if you need to connect the centers of a series of circles with a line.

You can specify one or more running object snaps on the Object Snaps tab in the Drafting Settings dialog box, which is accessible from the Tools menu. If several running object snaps are on, more than one object snap may be eligible at a given location. Press TAB to cycle through the possibilities before you specify the point.

Click the OSNAP button on the status bar or press F3 to turn running object snaps on and off.

*Note.* If you want object snaps to ignore hatch objects, set the OSOPTIONS system variable to 1.

**Object Snap Tab** (Drafting Settings Dialog Box) controls running object snap settings.

With running object snap settings, also called Osnap, you can specify a snap point at an exact location on an object. When more than one option is selected, the selected snap modes are applied to return a point closest to the center of the aperture box. Press TAB to cycle through the options.

### Object Snap On

Turns running object snaps on and off. The object snaps selected under Object Snap Modes are active while object snap is on. (OSMODE system variable)


### Object Snap Tracking On

Turns object snap tracking on and off. With object snap tracking, the cursor can track along alignment paths based on other object snap points when specifying points in a command. To use object snap tracking, you must turn on one or more object snaps. (AUTOSNAP system variable)

### Object Snap Modes

Lists object snaps that you can turn on as running object snaps.

*Endpoint* snaps to the closest endpoint of an arc, elliptical arc, line, multiline, polyline segment, spline, region, or ray, or to the closest corner of a trace, solid, or 3D face.




*Midpoint* snaps to the midpoint of an arc, ellipse, elliptical arc, line, multiline, polyline segment, region, solid, spline, or xline.




*Center* snaps to the center of an arc, circle, ellipse, or elliptical arc.






Node snaps to a point object, dimension definition point, or dimension text origin.



*Quadrant* snaps to a quadrant point of an arc, circle, ellipse, or elliptical arc.



*Intersection* snaps to the intersection of an arc, circle, ellipse, elliptical arc, line, multiline, polyline, ray, region, spline, or xline. Extended Intersection is not available as a running object snap.

Intersection and Extended Intersection do not work with edges or corners of 3D solids.



*Note.* You might get varying results if you have both the Intersection and Apparent Intersection running object snaps turned on at the same time.

*Extension* causes a temporary extension line or arc to be displayed when you pass the cursor over the endpoint of objects, so you can specify points on the extension.

*Note.* When working in perspective view, you cannot track along the extension line of an arc or elliptical arc.

*Insertion* snaps to the insertion point of an attribute, a block, a shape, or text.

*Perpendicular* snaps to a point perpendicular to an arc, circle, ellipse, elliptical arc, line, multiline, polyline, ray, region, solid, spline, or xline. Deferred Perpendicular snap mode is automatically turned on when the object you are drawing requires that you complete more than one perpendicular snap. You can use a line, arc, circle, polyline, ray, xline, multiline, or 3D solid edge as an object from which to draw a perpendicular line. You can use Deferred Perpendicular to draw perpendicular lines between such objects. When the aperture box passes over a Deferred Perpendicular snap point, an AutoSnap tooltip and marker are displayed.



*Tangent* snaps to the tangent of an arc, circle, ellipse, elliptical arc, or spline. Deferred Tangent snap mode is automatically turned on when the object you are

drawing requires that you complete more than one tangent snap. You can use Deferred Tangent to draw a line or xline that is tangent to arcs, polyline arcs, or circles. When the aperture box passes over a Deferred Tangent snap point, a marker and an AutoSnap tooltip are displayed.



*Note.* When you use the From option in conjunction with the Tangent snap mode to draw objects other than lines from arcs or circles, the first point drawn is tangent to the arc or circle in relation to the last point selected in the drawing area.

*Nearest* snaps to the nearest point on an arc, circle, ellipse, elliptical arc, line, multiline, point, polyline, ray, spline, or xline.

*Apparent Intersection* snaps to the visual intersection of two objects that are not in the same plane but may appear to intersect in the current view. Extended Apparent Intersection is not available as a running object snap. Apparent and Extended Apparent Intersection do not work with edges or corners of 3D solids.

*Note.* You might get varying results if you have both the Intersection and Apparent Intersection running object snaps turned on at the same time.

*Parallel* constrains a line segment, polyline segment, ray or xline to be parallel to another linear object. After you specify the first point of a linear object, specify the parallel object snap. Unlike other object snap modes, you move the cursor and hover over another linear object until the angle is acquired. Then, move the cursor back toward the object that you are creating. When the path of the object is parallel to the previous linear object, an alignment path is displayed, which you can use to create the parallel object.

*Note.* Turn off ORTHO mode before using the parallel object snap. Object snap tracking and polar snap are turned off automatically during a parallel object snap operation. You must specify the first point of a linear object before using the parallel object snap.

## Dynamic Input

Dynamic Input provides a command interface near the cursor to help you keep your focus in the drafting area.

When Dynamic Input is on, tooltips display information near the cursor that is dynamically updated as the cursor moves. When a command is active, the tooltips provide a place for user entry.

After you type a value in an input field and press TAB, the field then displays a lock icon, and the cursor is constrained by the value that you entered. You can then enter a value for the second input field. Alternately, if you type a value and press ENTER, the second input field is ignored and the value is interpreted as direct distance entry.

The actions required to complete a command or to use grips are similar to those for the command prompt. The difference is that your attention can stay near the cursor.

Dynamic Input is not designed to replace the command window. You can hide the command window to add screen area for drawing, but you will need to display it for some operations. Press F2 to hide and display command prompts and error messages as needed. Alternately, you can undock the command window and use Auto-hide to roll open or roll up the window.


## Turn Dynamic Input On and Off

Click Dyn on the status bar to turn Dynamic Input on and off. You can turn it off temporarily by holding down the F12 key. Dynamic Input has three components: pointer input, dimensional input, and dynamic prompts. Right-click Dyn and click Settings to control what is displayed by each component when Dynamic Input is on.

### Pointer Input

When pointer input is on and a command is active, the location of the crosshairs is displayed as coordinates in a tooltip near the cursor. You can enter coordinate values in the tooltip instead of on the command line.


The default for second and subsequent points is relative polar coordinates (relative Cartesian for RECTANG). There is no need to type the at sign (@). If you want to use absolute coordinates, use the pound sign (#) prefix. For example, to move an object to the origin, for the second point prompt, enter #0,0.



Use the pointer input settings to change the default format for coordinates and to control when pointer input tooltips are displayed.


### Dimensional Input

When dimensional input is on, the tooltips display distance and angle values when a command prompts for a second point. The values in the dimensional tooltips change as you move the cursor. Press TAB to move to the value you want to change. Dimensional input is available for ARC, CIRCLE, ELLIPSE, LINE, and PLINE.



When you use grips to edit an object, the dimensional input tooltips can display the following information:

- Original length
- A length that updates as you move the grip
- The change in the length
- Angle
- The change in the angle as you move the grip
- The radius of an arc



Use the dimensional input settings to display only the information you want to see.

When you use grips to stretch objects or when you create new objects, dimensional input displays only acute angles, that is, all angles are displayed as 180 degrees or less. Thus, an angle of 270 degrees is displayed as 90 degrees regardless of the ANGDIR system variable setting (set in the Drawing Units dialog box). Angles specified when creating new objects rely on the cursor location to determine the positive angle direction.

## Dynamic Prompts

When dynamic prompts are on, prompts are displayed in a tooltip near the cursor. You can enter a response in the tooltip instead of on the command line. Press the DOWN ARROW key to view and select options. Press the UP ARROW key to display recent input.



*Note.* To use PASTECLIP in a dynamic prompt tooltip, type a letter and then backspace to delete it before you paste the entry. Otherwise, the entry is pasted into the drawing as text.

Dynamic Input Tab (Drafting Settings Dialog Box) controls pointer input, dimension input, dynamic prompting, and the appearance of drafting tooltips.

#### Enable Pointer Input

Turns on pointer input. When pointer input and dimensional input are both turned on, dimensional input supersedes pointer input when it is available. (DYNMODE system variable)

#### Pointer Input

Displays the location of the crosshairs as coordinate values in a tooltip near the cursor. When a command prompts for a point, you can enter coordinate values in the tooltip instead of on the command line.

*Preview Area* shows an example of pointer input.

*Settings* Displays the Pointer Input Settings dialog box.

#### Enable Dimension Input

Turns on dimensional input. Dimensional input is not available for some commands that prompt for a second point. (DYNMODE system variable)

#### Dimension Input

Displays a dimension with tooltips for distance value and angle value when a command prompts for a second point or a distance. The values in the dimension tooltips change as you move the cursor. You can enter values in the tooltip instead of on the command line.

*Preview Area* shows an example of dimensional input.

*Settings* displays the Dimension Input Settings dialog box.

#### Dynamic Prompts

Displays prompts in a tooltip near the cursor when necessary in order to complete the command. You can enter values in the tooltip instead of on the command line.

*Preview Area* shows an example of dynamic prompts.

*Show Command Prompting and Command Input near the Crosshairs* displays prompts in Dynamic Input tooltips. (DYNPROMPT system variable)

# **Lecture #8.**

## **Working with a text in the AutoCAD program**

### **Overview of Creating Text**

The text you add to your drawings conveys a variety of information. It may be a complex specification, title block information, a label, or even part of the drawing.

#### Single-Line Text

For short entries that do not require multiple fonts or lines, create single-line text. Single-line text is most convenient for labels.

#### Multiline Text

For long, complex entries, create multiline, or paragraph text. Multiline text consists of any number of text lines or paragraphs that fit within a width you specify; it can extend vertically to an indefinite length.

Regardless of the number of lines, each set of paragraphs created in a single editing session forms a single object, which you can move, rotate, erase, copy, mirror, or scale.

There are more editing options for multiline text than there are for single-line text. For example, you can apply underlining, fonts, color, and text height changes to individual characters, words, or phrases within a paragraph.

#### Annotative Text

Use annotative text for notes and labels in your drawing. You create annotative text by using an annotative text style, which sets the height of the text on the paper.

For more information about creating and working with an annotative text, see *Create Annotative Text*.

### **Create Single-Line Text**

You can use single-line text to create one or more lines of text, where each text line is an independent object that you can relocate, reformat, or otherwise modify.

Use single-line text (TEXT) to create one or more lines of text, ending each line when you press ENTER. Each text line is an independent object that you can relocate, reformat, or otherwise modify.

When you create single-line text, you assign a text style and set alignment. The text style sets the default characteristics of the text object. The alignment determines what part of the text character aligns with the insertion point. Use the TEXT command to enter the text in-place, or enter -text on the command line to enter the text on the command line.

You can insert a field in single-line text. A field is text that is set up to display data that might change. When the field is updated, the latest value of the field is displayed.

The text styles used for single-line text are the same as those used for multiline text. When you create text, you assign an existing style by entering its name at the


Style prompt. If you need to apply formatting to individual words and characters, use multiline text instead of single-line text.

You can also compress single-line text to fit between points that you specify. This option stretches or squeezes the text to fill the designated space.

The DTEXTED system variable specifies the user interface displayed for editing single-line text.

### Align Single-Line Text

As you create text, you can align it. That is, you can justify it with one of the alignment options shown in the following illustrations. Left alignment is the default. To left-align text, do not enter an option at the Justify prompt.



The TEXT command creates a single-line text object.

Menu: Draw ► Text ► Single Line Text

Command entry: text

It displays a simplified version of the In-Place Text Editor that consists of a bounding box that is the height of the text and expands as you type. Right-click to select options on the shortcut menu.

If TEXT was the last command entered, pressing ENTER at the Specify Start Point of Text prompt skips the prompts for paper height and rotation angle. The text that you enter in the In-Place Text Editor for single-line text is placed directly

beneath the previous line of text. The point that you specified at the prompt is also stored as the insertion point of the text.

If the `DTEXTED` system variable is set to 1, text created using `TEXT` or `DTEXT` displays the Edit Text dialog box.

If `DTEXTED` is set to 2, the In-Place Text Editor is displayed. When creating text, you can click anywhere in a drawing to create a new text block. You can also use the keyboard to move among text blocks (for example: for new text created using the `TEXT` command, you can navigate through text groups by pressing `TAB` or `Shift+TAB`, or edit a group of text lines by pressing `ALT` and clicking each text object.)

*Note.* Text that would otherwise be difficult to read (if it is very small, very large, or is rotated) is displayed at a legible size and is oriented horizontally so that you can easily read and edit it.

You can enter special characters and format text by entering Unicode strings and control codes.

Use `-TEXT` to honor the `TEXTVAL` system variable.

`DTEXT` is the same as `TEXT`.

## **Create Multiline Text**

You can create one or more paragraphs of multiline text (`mtext`) in the In-Place Text Editor (or an alternative text editor) or use prompts on the command line. You can also insert text from a file saved in ASCII or RTF format.

Before entering or importing text, you specify opposite corners of a text bounding box that defines the width of the paragraphs in the multiline text object. The length of the multiline text object depends on the amount of text, not the length of the bounding box. You can use grips to move or rotate a multiline text object.

The In-Place Text Editor displays the bounding box with a ruler at the top and the Text Formatting toolbar. The editor is transparent so that, as you create text, you can see whether the text overlaps other objects. To turn off transparency while you work, select `Opaque Background` on the `Options` menu. You can also make the background of the finished multiline text object opaque and set its color.

You can also insert fields in multiline text. A field is text that is set up to display data that might change. When the field is updated, the latest value of the field is displayed.

## **Text Style**

Most characteristics of the text are controlled by the text style, which sets the default font and other options, such as line spacing, justification, and color. You can use the current text style or select a new one. The `STANDARD` text style is the default.

Within the multiline text object, you can override the current text style by applying formatting such as underlining, boldface, and different fonts to individual



characters. You can also create stacked text, such as fractions or geometric tolerances and insert special characters, including Unicode characters, for TrueType fonts.

*Note.* Not all SHX and TrueType text fonts support Unicode characters.

## Text Properties


In the Properties palette, you can view and change the object properties of a multiline text object, including properties that apply specifically to text.

- Justification determines where text is inserted with respect to the bounding box and sets the direction of text flow as text is entered.
- Line space options control the amount of space between lines of text.
- Width defines the width of the bounding box and therefore controls where the text wraps to a new line.
- Background inserts an opaque background so that objects under the text are masked.

## Justify Multiline Text

Justification of multiline text objects controls both text alignment and text flow relative to the text insertion point.

There are nine justification settings for multiline text.



Justification controls both text alignment and text flow relative to the text insertion point. Text is left-justified and right-justified with respect to the boundary

rectangle that defines the text width. Text flows from the insertion point, which can be at the middle, the top, or the bottom of the resulting text object.

If a single word is longer than the width of the paragraph, the word will extend beyond the paragraph boundary.

### **In-Place Text Editor**

The MTEXT command creates paragraphs of text as a single multiline text (mtext) object

Toolbar: Draw 

Menu: Draw ► Text ► Multiline Text

Pointing device: Double-click a multiline text object.

Command entry: mtext


Dashboard: Text panel, Multiline Text

After you specify the point for the opposite corner, the in-place text editor is displayed.

If you specify one of the other options, or if you enter -mtext at the command prompt, MTEXT bypasses the In-Place Text editor and displays additional command prompts.

In-Place Text Editor Creates or modifies single or multiline text objects. You can import or paste text from other files to use in multiline text, set tabs, adjust paragraph and line spacing and alignment, and create and modify columns.

The In-Place Text Editor includes a Text Formatting Toolbar, a Paragraph Dialog Box, a Columns Menu, and an Display Options Menu. When a table cell is selected for editing, the In-Place Text Editor displays column letters and row numbers.



## Text Formatting Toolbar

Controls the text style for a multiline text object and character and paragraph formatting for selected text.

*Note.* Text that you paste from other word processing applications such as Microsoft Word will retain most of its formatting. With the options in Paste Special, you can strip out paragraph formatting such as paragraph-based alignment or character formatting from the pasted text.

## Display Options Menu

Changes the behavior of the Text Formatting toolbar and provides additional editing options. Options are specific to the Display Options menu and are not available on the Text Formatting toolbar.

*Note.* Some options may not be available depending on what you are editing.

### Show Toolbar

Controls display of the Text Formatting toolbar. To restore display of the toolbar, right-click in the editor and click Option ▸ Show Toolbar.

### Show Options

Expands the Text Formatting toolbar to show more options.

### Show Rulers

Controls the display of the ruler.

### Opaque Background

When selected, makes the background of the editor opaque. By default, the editor is transparent. (Not available for table cells.)

### Text Highlight Color

Displays the AutoCAD generic Select Color dialog box. Specifies the highlight color when text is selected.

## **Lecture #9.**

### **Building floor plans and facades computer-aided design.**

#### **Create Single-View Drawings (Model Space)**

If you are going to create a two dimensional drawing that has one view, you can create the drawing and its annotation entirely in model space. This is the traditional method for creating drawings with AutoCAD.

#### **Model Space Drafting**

The process of creating and plotting a drawing file in model space is very different from the process used in manual drafting.

In AutoCAD, there are two distinct working environments that are represented by the Model and layout tabs. These tabs are located near the bottom of the drawing area.

If you are going to create a two-dimensional drawing that has one view, you can create both the model and its annotation entirely in model space, not using a layout tab. This is the traditional method for creating drawings with AutoCAD. This method is simple but has several limitations, including

- It is suitable for 2D drawings only.
- It does not support multiple views and view-dependent layer settings.
- Scaling the annotation and title block requires computation unless you use annotative objects.

With this method, you always draw geometric objects at full scale (1:1) and text, dimensions, and other annotation at a scale that will appear at the correct size when the drawing is plotted.

#### **Draw, Scale, and Annotate in Model Space**

If you draw and plot from model space, you must determine and apply a scale factor to annotate objects before you plot.

You can draw and plot entirely from model space. This method is useful primarily for two-dimensional drawings that have a single view. With this method, you use the following process:

- Determine the unit of measurement (drawing units) for the drawing.
- Specify the display style for the drawing unit.
- Calculate and set the scale for dimensions, annotations, and blocks.
- Draw at full scale (1:1) in model space.
- Create the annotation and insert the blocks in model space.

- Plot the drawing at the predetermined scale.

You can also use annotative objects if you want to scale annotations automatically. For information about using annotative objects and scaling annotations automatically, see *Scale Annotations*.

#### Determine the Unit of Measurement

Before you begin drawing in model space, you determine the unit of measurement (drawing units) that you plan to use. You decide what each unit on the screen represents, such as an inch, a millimeter, a kilometer, or some other unit of measurement. For example, if you are drawing a motor part, you might decide that one drawing unit equals a millimeter. If you are drawing a map, you might decide that one unit equals a kilometer.

For architectural projects you might decide that one unit equals a meter.

#### Specify the Display Style of Drawing Units

Once you have determined a drawing unit for the drawing, you need to specify the style for displaying the drawing unit, which includes the unit type and precision. For example, a value of 14.5 can be displayed as 14.500, 14-1/2, or 1'2-1/2".

Specify the display style of drawing units with the UNITS command. The default drawing unit type is decimal.

#### Set the Scale for Annotations and Blocks

Before you draw, you should set the scale for dimensions, annotations, and blocks in your drawings. Scaling these elements beforehand ensures that they are at the correct size when you plot the final drawing.

You should enter the scale for the following objects:

*Text.* Set the text height as you create text or by setting a fixed text height in the text style (STYLE).

*Dimensions.* Set the dimension scale in a dimension style (DIMSTYLE) or with the DIMSCALE system variable.

*Linetypes.* Set the scale for noncontinuous linetypes with the CELTSCALE and LTSCALE system variables.

*Hatch patterns.* Set the scale for hatch patterns in the Hatch and Gradient dialog box (HATCH) or with the HPSCALE system variable.

*Blocks.* Specify the insertion scale for blocks either as you insert them, or set an insertion scale in the Insert dialog box (INSERT) or in DesignCenter (ADCENTER). The system variables used for inserting blocks are INSUNITS, INSUNITSDEFSOURCE, and INSUNITSDEFTARGET. This also applies to the border and title block of the drawing.

You can also use annotative objects if you want to scale annotations automatically. For information about using annotative objects and scaling annotations automatically, see *Scale Annotations*.

#### Determine the Scale Factor for Plotting

To plot your drawing from the Model tab, you calculate the exact scale factor by converting the drawing scale to a ratio of 1:n. This ratio compares plotted units to drawing units that represent the actual size of the objects you are drawing.

For example, if you plan to plot at a scale of 1/4 inch = 1 foot, you would calculate the scale factor 48 as follows:

$$1/4" = 12"$$

$$1 = 12 \times 4$$

$$1 \text{ (plotted unit)} = 48 \text{ (drawing units)}$$

Using the same calculation, the scale factor for 1 centimeter = 1 meter is 100, and the scale factor for 1 inch = 20 feet is 240.

## Create Multiple-View Drawing Layouts (Paper Space)

Paper space is a sheet layout environment where you can specify the size of your sheet, add a title block, display multiple views of your model, and create dimensions and notes for your drawing.


### Understand the Layout Process

There are two distinct working environments, or “spaces,” in which you can create objects in a drawing. These are represented by the Model and layout tabs.

Typically, a model composed of geometric objects is created in a three-dimensional space called model space. A final layout of specific views and annotations of this model is created in a two-dimensional space called paper space. These spaces are accessible on two or more tabs near the bottom of the drawing area: the Model tab and one or more layout tabs.

*Note.* These tabs can be hidden, appearing instead as buttons on the status bar at the bottom-center of the application window.

Working on the Model tab, you draw a model of your subject at 1:1 scale. Working on a layout tab, you can create one or more layout viewports, dimensions, notes, and a title block to represent a drawing sheet.



Each layout viewport is like a picture frame containing a “photograph” of the model in model space. Each layout viewport contains a view that displays the model at the scale and orientation that you specify. You can also specify which layers are visible in each layout viewport.

After you finish arranging the layout, you turn off the layer that contains the layout viewport objects. The views are still visible, and you can plot the layout without displaying the viewport boundaries.

When you use a layout tab to prepare your drawing for plotting, you follow a series of steps in a process.

You design the subject of your drawing on the Model tab (in model space) and prepare it for plotting on a layout tab (in paper space).

There is one Model tab and one or more layout tabs at the bottom of the drawing window.

*Note.* These tabs can be hidden, appearing instead as buttons on the status bar at the bottom-center of the application window.

### Process Summary

When you prepare a layout, you typically step through the following process:

- Create a model of your subject on the Model tab.
- Click a layout tab.
- Specify layout page settings such as plotting device, paper size, plot area, plot scale, and drawing orientation.
- Insert a title block into the layout (unless you have started with a drawing template that already has a title block).
- Create a new layer to be used for layout viewports.
- Create layout viewports and position them on the layout.
- Set the orientation, scale, and layer visibility of the view in each layout viewport.
- Add dimensions and annotate in the layout as needed.
- Turn off the layer containing the layout viewports.
- Plot your layout.

You can also use annotative objects if you want to annotate your drawing in model space and scale the annotations automatically. For information about using annotative objects and scaling annotations automatically, see *Scale Annotations*.

## **Work with Model Space and Paper Space**

There are several benefits to switching between model space and paper space to perform certain tasks. Use model space for creating and editing your model. Use paper space for composing your drawing sheet and defining views.

### Work on the Model Tab

The Model tab accesses a limitless drawing area called model space. In model space, you draw, view, and edit your model.

In model space, you draw your model at 1:1 scale, and you decide whether one unit represents one millimeter, one centimeter, one inch, one foot, or whatever unit is most convenient or customary in your business.


On the Model tab, you can view and edit model space objects. The crosshairs cursor is active over the entire drawing area.

### Work on a Layout Tab

Layout tabs access an area called paper space. In paper space, you place your title block, create layout viewports to display views, dimension your drawing, and add notes.

In paper space, one unit represents the paper distance on a plotted sheet. The units will be in either millimeters or inches, depending on the plot setup for your plotter.

On a layout tab, you can view and edit paper space objects, such as layout viewports and title blocks. You can also move an object (such as a leader or a title block) from model space to paper space (or vice versa). The crosshairs cursor is active over the entire layout area.



Note. These tabs can be hidden, appearing instead as buttons on the status bar at the bottom-center of the application window. To display the tabs, right-click the Model or layout button and click Display Layout and Model Tabs on the shortcut menu.

### Access Model Space from a Layout Viewport

You can access model space from a layout viewport to edit objects, to freeze and thaw layers, and to adjust the view.

After creating viewport objects, you can access model space from a layout viewport to perform the following tasks:

- Create and modify objects in model space inside the layout viewport.
- Pan the view inside the layout viewport and change layer visibility.

The method you use to access model space depends on what you plan to do.

### **Create and Modify Objects in a Layout Viewport**

If you plan to create or modify objects, use the button on the status bar to maximize the layout viewport. The maximized layout viewport expands to fill the drawing area. The center point and the layer visibility settings of the viewport are retained, and the surrounding objects are displayed.

You can pan and zoom while you are working in model space, but when you restore the viewport to return to paper space, the position and scale of the objects in the layout viewport are restored.



*Note.* If you use PLOT while a viewport is maximized, the layout tab is restored before the Plot dialog box is displayed. If you save and close the drawing while a viewport is maximized, the drawing opens with the layout tab restored.

If you choose to switch to the Model tab to make changes, the layer visibility settings are the settings for the drawing as a whole, not the settings for that particular layout viewport. Also, the view is not centered or magnified the same way it is in the layout viewport.

### **Adjust the View in a Layout Viewport**

If you plan to pan the view and change the visibility of layers, double-click within a layout viewport to access model space. The viewport border becomes thicker, and the crosshairs cursor is visible in the current viewport only. All active viewports in the layout remain visible while you work. You can freeze and thaw layers in the current viewport in the Layer Properties Manager, and you can pan the view. To return to paper space, double-click an empty area on the layout outside a viewport. The changes you made are displayed in the viewport.


If you set the scale in the layout viewport before you access model space, you can lock the scale to prevent changes. When the scale is locked, you cannot use ZOOM while you work in model space.

### **Create and Modify Layout Viewports**

You can create a single layout viewport that fits the entire layout or create multiple layout viewports in the layout. Once you create the viewports, you can change their size, their properties, and also scale and move them as needed.

*Note.* It is important to create layout viewports on their own layer. When you are ready to plot, you can turn off the layer and plot the layout without plotting the boundaries of the layout viewports.

With MVIEW, you have several options for creating one or more layout viewports. You can also use COPY and ARRAY to create multiple layout viewports.



### Create Nonrectangular Layout Viewports

You can create a new viewport with nonrectangular boundaries by converting an object drawn in paper space into a layout viewport.

The MVIEW command provides two options to assist you in defining an irregularly shaped viewport.

With the Object option, you can select a closed object, such as a circle or closed polyline created in paper space, to convert into a layout viewport. The object that defines the viewport boundary is associated with the viewport after the viewport is created.

The Polygonal option can be used to create a nonrectangular layout viewport by specifying points. The prompt sequence is the same as the prompt sequence for creating a polyline.

*Note.* When you want to suppress the display of the boundary of a layout viewport, you should turn off the layer of the nonrectangular viewport instead of freezing it. If the layer of a nonrectangular layout viewport is frozen, the boundary is not displayed, but the viewport is not clipped.

### Resize Layout Viewports

If you want to change the shape or size of a layout viewport, you can use grips to edit the vertices just as you edit any object with grips.

### Clip Layout Viewports

You can redefine the boundary of a layout viewport by using the VPCLIP command. To clip a layout viewport, you can use your pointing device to either select an existing object to designate as the new boundary, or specify the points of a new boundary.

## **Control Views in Layout Viewports**

When you create a layout, you can add layout viewports that act as windows into model space. In each layout viewport, you can control the view that is displayed.

### **Scale Views in Layout Viewports**

To scale each displayed view in the plotted drawing accurately, set the scale of each view relative to paper space.

You can change the view scale of the viewport using

- The Properties palette
- The XP option of the ZOOM command
- The Viewports toolbar

*Note.* You can modify the list of scales that are displayed in all view and plot scale lists with SCALELISTEDIT.

When you work in a layout, the scale factor of a view in a layout viewport represents a ratio between the actual size of the model displayed in the viewport and the size of the layout. The ratio is determined by dividing the paper space units by the

model space units. For example, for a quarter-scale drawing, the ratio would be a scale factor of one paper space unit to four model space units, or 1:4.

Scaling or stretching the layout viewport border does not change the scale of the view within the viewport.

### **Lock the Scale of Layout Viewports**

Once you set the viewport scale, you cannot zoom within a viewport without changing the viewport scale. By locking the viewport scale first, you can zoom in to view different levels of detail in your viewport without altering the viewport scale.

Scale locking locks the scale that you set for the selected viewport. Once the scale is locked, you can continue to modify the geometry in the viewport without affecting the viewport scale. If you turn a viewport's scale locking on, most of the viewing commands, such as VPOINT, DVIEW, 3DORBIT, PLAN, and VIEW, no longer function in that viewport.

*Note.* Viewport scale locking is also available for nonrectangular viewports. To lock a nonrectangular viewport, you must perform an extra step in the Properties palette to select the viewport object rather than the viewport clipping boundary.


### **Control Visibility in Layout Viewports**

You can control the visibility of objects in layout viewports using several methods. These methods are useful for emphasizing or hiding different elements of a drawing, and for reducing screen regeneration time.

### **Freeze Specified Layers in a Layout Viewport**

A major benefit to using layout viewports is that you can selectively freeze layers in each layout viewport. You can also specify default visibility settings for new viewports and for new layers. As a result, you can view different objects in each layout viewport.

You can freeze or thaw layers in current and future layout viewports without affecting other viewports. Frozen layers are invisible. They are not regenerated or plotted. In the illustration, the layer showing terrain has been frozen in one viewport.



Thawing the layer restores visibility. The easiest way to freeze or thaw layers in the current viewport is to use the Layer Properties Manager.

In the Layer Properties Manager, on the right side, use the column labeled VP Freeze to freeze one or more layers in the current layout viewport. To display the VP Freeze column, you must be on a layout tab. Specify the current layout viewport by double-clicking anywhere within its borders.

### **Freeze or Thaw Layers Automatically in New Layout Viewports**

You can set visibility defaults for specific layers in all new layout viewports. For example, you can restrict the display of dimensions by freezing the DIMENSIONS layer in all new viewports. If you create a viewport that requires dimensions, you can override the default setting by changing the setting in the current viewport. Changing the default for new viewports does not affect existing viewports.

### **Create New Layers That Are Frozen in All Layout Viewports**

You can create new layers that are frozen in all existing and new layout viewports. Then you can thaw the layers in the viewports you specify. This is a shortcut for creating a new layer that is visible only in a single viewport.

### **Screen Objects in Layout Viewports**

Screening refers to applying less ink to an object when it is plotted. The object appears dimmer on the screen and on the plotted paper. Screening can be used to help differentiate objects in a drawing without changing the objects' color properties.

To assign a screening value to an object, you must assign a plot style to the object, and then define the screening value in that plot style.


You can assign a screening value from 0 to 100. The default setting, 100, means no screening is applied, and the object is displayed with normal ink intensity. A screening value of 0 means the object contains no ink and is thus invisible in that viewport.

### **Turn Layout Viewports On or Off**

You can save time by turning some layout viewports off or by limiting the number of active viewports.

Displaying a large number of active layout viewports can affect your system's performance as the content of each layout viewport regenerates. You can save time by turning some layout viewports off or by limiting the number of active viewports. The following illustration shows the effects of turning off two layout viewports.

New layout viewports are turned on by default. If you turn off the layout viewports you aren't using, you can copy layout viewports without waiting for each one to regenerate.




If you don't want to plot a layout viewport, you can turn the layout viewport off.

### Scale Linetypes in Layout Viewports

You can scale linetypes in paper space either based on the drawing units of the space in which the object was created or based on the paper space units.

You can set the PSLTSCALE system variable to maintain the same linetype scaling for objects displayed at different zoom factors in a layout and in a layout viewport. For example, with PSLTSCALE set to 1 (default), set the current linetype to dashed, and then draw a line in a paper space layout. In the layout, create a viewport with a zoom factor of 1x, make that layout viewport current, and then draw a line using the same dashed linetype. The dashed lines should appear to be the same. If you change the viewport zoom factor to 2x, the linetype scaling for the dashed line in the layout and the dashed line in the layout viewport will be the same, regardless of the difference in the zoom factor.




With PSLTSCALE turned on, you can still control the dash lengths with LTSCALE and CELTSCALE. In the following illustration, the pattern of the linetypes in the drawing on the left has been scaled to be the same regardless of the scale of the view. In the drawing on the right, the scale of the linetypes matches the scale of each view.

### Align Views in Layout Viewports



You can arrange the elements of your drawing by aligning the view in one layout viewport with the view in another viewport.

For angled, horizontal, and vertical alignments, you can move each layout viewport relative to distances defined by the model-space geometry displayed.



To adjust the views on a layout with precision, you can create construction geometry, use object snaps on the model-space objects displayed in layout viewports, or use one of the cursor constraint features available on the status bar.




Horizontal alignments



Vertical alignments




Angled alignments




## Rotate Views in Layout Viewports

You can rotate an entire view within a layout viewport by changing the UCS and using the PLAN command.

With the UCS command, you can rotate the XY plane at any angle around the Z axis. When you enter the PLAN command, the view rotates to match the orientation of the XY plane.



original view



rotated view

For a faster method, use the Align and then Rotate View options in the MVSETUP command.


*Note.* The ROTATE command rotates individual objects only and should not be used to try to rotate a view.

### Work with Sheets in a Sheet Set


With the Sheet Set Manager, you can organize drawing layouts into named sheet sets. The sheets in a sheet set can be transmitted, published, and archived as a unit.

A sheet set is an organized collection of sheets from several drawing files. A sheet is a selected layout from a drawing file.

Sets of drawings are the primary deliverable for most design groups. Sets of drawings communicate the overall design intent of a project and provide the documentation and specifications for the project. However, managing sets of drawings manually can be complicated and time consuming.



With the Sheet Set Manager, you can manage drawings as sheet sets. A sheet set is an organized and named collection of sheets from several drawing files. A sheet is a selected layout from a drawing file. You can import a layout from any drawing into a sheet set as a numbered sheet.



You can manage, transmit, publish, and archive sheet sets as a unit.

Using the controls in the Sheet Set Manager, you can create, organize, and manage sheets in a sheet set.



*Навчальне видання*

**БОЧАРОВ** Борис Петрович

**Конспект лекцій**

*з дисципліни*

**«КОМП'ЮТЕРНА ГРАФІКА»**

*(для студентів 2 курсу спеціальності  
122 – Комп'ютерні науки та інформаційні технології)*

*(англ. мовою)*

Відповідальний за випуск : *М. В. Булаєнко*

За авторської редакцією

Комп'ютерне верстання *Б. П. Бочаров*

План 2016, поз. 201Л

---

Підп. до друку 06.12.2016  
Друк на ризографі  
Зам №

Формат 60x84/16  
Ум. друк. арк. 4,0  
Тираж 30 пр.

Видавець і виготовлювач:  
Харківський національний університет  
міського господарства імені О. М. Бекетова  
Вул. Революції, 12, Харків, 61002  
Електронна адреса: [rectorat@kname.edu.ua](mailto:rectorat@kname.edu.ua)  
Свідоцтво суб'єкта видавничої справи  
ДК № 4705 від 28.03.2014 р.